

Agency Owner & Manager Guide

Complete guide to managing your agency
through the Sales CRM dashboard

July 2026

Sales CRM - Agency Dashboard

Table of Contents

1. **Getting Started & First Login**
2. **The Manager Dashboard - Agency Overview**
3. **Managing Leads - Upload, Assign & Filter**
4. **Leaderboard - Tracking Rep Performance**
5. **Admin Users - Managing Your Team**
6. **Pipeline Overview**
7. **Email Sequences - Automated Follow-ups**
8. **Settings - Managing Your Account**
9. **Notifications**
10. **Technical Reference - Deployment & Maintenance**

1. Getting Started & First Login

1.1 Accessing the CRM

Open the CRM URL in your browser. On the login screen, sign in with your manager credentials.

1.2 Login Credentials

Use the credentials provided by your system administrator to sign in. The following accounts are available:

Manager Account:

admin@agency.com / @Admin12345

Sales Reps:

ashba@agency.com / @Admin12345

jai@agency.com / @Admin12345

agnas@agency.com / @Admin12345

IMPORTANT:

Change the default passwords immediately after first login, especially the admin account.

1.3 Navigation for Managers

After signing in, you are redirected to the Manager Dashboard. The sidebar includes:

- Dashboard - Agency performance overview
- Leads - Full lead management (upload, assign, filter, export)
- Leaderboard - Rep performance rankings
- Users - Manage team members (add/deactivate)
- Settings - Change your password

2. The Manager Dashboard

The Manager Dashboard gives you a real-time overview of your entire agency's performance.

2.1 KPI Cards

- Total Calls - Total calls made by all reps
- Success Rate - Overall percentage of calls that resulted in deals
- Deals Closed - Total deals closed across the agency
- Commissions Owed - Total commission earned by all reps

2.2 Date Range Filter

Use the 7D, 30D, 90D, or All buttons to filter the displayed data by time period.

2.3 Charts & Visualizations

- Calls by Rep - Bar chart comparing calls and deals per rep
- Weekly Trend - Area chart showing call activity over the week
- Lead Distribution - Pie chart showing lead status distribution

2.4 Rep Performance Table

A table listing each rep with: leads count, calls made, deals closed, success rate (shown as a color-coded badge), and commission earned. Sortable by clicking column headers.

2.5 Sales Pipeline Overview

A grid of all pipeline stages showing the number of leads at each stage and the names of the first few leads, with an overflow indicator for additional leads.

2.6 Activity Feed

A chronological list of recent activities across all reps, showing call outcomes, deals closed, and other important events.

3. Managing Leads

The Leads page is the central hub for managing all leads in the system. This is where you import, assign, filter, and oversee all client prospects.

3.1 Uploading Leads (CSV Import)

Click the "Upload CSV" button to import leads in bulk. The system accepts:

- File formats: .csv, .xlsx, .xls
- Maximum file size: 10MB
- Columns: business_name, contact_name, phone (required); email, website (optional)

Uploaded leads are created with "Uncalled" status and not assigned to any rep.

3.2 Assigning Leads to Reps

You can assign leads to your sales reps in two ways:

- Bulk Assign: Select multiple leads using checkboxes, click the "Assign" button in the bulk actions toolbar, choose a rep from the dialog, and click "Assign"
- Individual: Assign leads one at a time through the lead detail dialog

3.3 Filtering & Searching

The FilterBar provides powerful search and filter capabilities:

- Search: Type to search by business name, contact name, or phone number
- Status Filter: Multi-select dropdown to filter by one or more pipeline stages
- Saved Filters: Save your current filter configuration for quick reuse
- Active Filter Badges: Show current filters with X buttons to remove individual filters

3.4 Lead Detail View

Click the three-dot menu on any lead row and select "View Details" to open the detail dialog. From here you can:

- View all lead information (business name, contact, phone, email, website, created date)
- Edit the lead status from the dropdown (all pipeline stages available)
- Update the deal value
- Add or edit notes

3.5 Exporting Leads

- Export All: Click "Export All" to download all leads as a CSV file
- Export Selected: Select specific leads and click "Export" in the bulk actions toolbar

3.6 Deleting Leads

- Single Delete: Use the three-dot menu and select Delete (with confirmation dialog)
- Bulk Delete: Select multiple leads and click "Delete" in the bulk actions toolbar

3.7 View Options

The leads table supports pagination with rows per page options (25/50/100). On mobile devices, leads are displayed as cards instead of a table for better readability.

MANAGER TIP:

Use saved filters for common views like "All Uncalled Leads" or "Leads with No Answer".

4. Leaderboard

The Leaderboard page helps you track and compare your reps' performance. Use it in team meetings to motivate and recognize top performers.

4.1 Sort Options

Click the sort toggle buttons to rank reps by different metrics:

- Deals - Most deals closed (trophy icon)
- Commission - Highest commission earned (\$ icon)
- Success Rate - Best call-to-deal conversion (trending icon)

4.2 Podium (Top 3)

The top 3 performers appear in a podium layout with animated gradient cards and gold/silver/bronze borders. Each card shows:

- Rank (with medal emoji)
- Rep name
- Deals closed count
- Commission earned
- Total calls made
- Success rate percentage

4.3 Full Rankings Table

Below the podium, all reps are listed in a table with: rank number, name, leads, calls, deals count (green badge), active pipeline count, success rate (with animated progress bar), and commission.

4.4 Chart

A "Deals by Rep" bar chart provides a visual comparison of how many deals each rep has closed.

5. Admin Users - Managing Your Team

The Users page lets you manage all team members who have access to the CRM.

5.1 Adding a New User

- Click the "Add User" button
- Fill in: Full Name, Email Address, Password (minimum 8 characters)
- Select Role: Sales Rep or Manager
- Click "Create User"

The new user will be able to sign in immediately with their email and password.

5.2 User List

The user list shows all team members (both managers and reps). For each user you can see:

- Name and email address
- Role (Sales Rep or Manager)
- Status badge - Active (green) or Inactive (gray)

5.3 Deactivating a User

Click the user icon next to any user to toggle their active status. Deactivated users cannot sign in to the CRM. This is useful when a team member leaves or is on extended leave.

NOTE:

Deactivating a user preserves their data and lead assignments. Reactivate them anytime by clicking again.

6. Pipeline Overview

The pipeline overview shows the complete sales funnel across all reps, giving you visibility into every lead's progress.

Uncalled	- Fresh leads not yet contacted
No Answer	- Calls made but no answer
Not Interested	- Lead declined
Interested	- Lead interested, needs demo
Pitching	- Active pitch in progress
Demo Scheduled	- Demo booked
Demo Completed	- Demo done
Negotiation	- Negotiating terms
Onboarding	- Client onboarding
Deposit Paid	- Deposit received
In Progress	- Project active (post-handover)
Deal Closed	- Closed won

Commission Model

Reps earn 20% commission on every deal they close. Commission is calculated automatically.

7. Email Sequences - Automated Follow-ups

Email Sequences allow you to create automated email campaigns that trigger based on lead status changes. This feature helps maintain consistent follow-up with leads without manual effort.

7.1 Creating a New Sequence

- Go to the Email Sequences page from the sidebar
- Click the "New Sequence" button
- Enter a Sequence Name (e.g. "New Lead Welcome")
- Add a Description explaining the sequence purpose
- Choose the Trigger - when the sequence should start:
 - Lead Assigned: Starts when a lead is assigned to a rep
 - Status Change: Starts when a lead enters a specific stage
 - Manual: Triggered manually by the rep
- If using "Status Change", select the trigger stage
- Click "Save Sequence" to create it

7.2 Building Sequence Steps

After creating a sequence, add steps using the Sequence Builder:

- **Send Email:** Compose an email with subject and body. The email will be sent to the lead's email address automatically.
- **Delay:** Wait a specified number of days before the next step (e.g. wait 3 days after the initial email).
- **Update Stage:** Automatically advance the lead to a new pipeline stage after this step completes.
- **Notify:** Send a notification to a manager or the assigned rep.
- **Condition:** Branch based on lead data (e.g. only send if lead is interested).

Steps execute in order. Use the delay step strategically to space out communications. You can reorder steps by editing step numbers in the builder.

7.3 Viewing Email Logs

The Logs tab shows all emails sent by the system, including:

- Recipient email address
- Email subject line
- Sent date and time
- Delivery status (sent/failed)
- Open and click tracking (if available)

Use the sequence filter to view logs for a specific sequence, or view all logs together.

7.4 Managing Sequences

From the Email Sequences page, you can:

- View all sequences in a list with their name, description, and active status
- Click a sequence to open its detail view with step builder and logs
- Toggle a sequence on/off using the active switch
- Delete sequences that are no longer needed

Only active sequences will execute their steps when triggered. Inactive sequences remain saved but do not send emails.

TIP:

Start with a simple welcome sequence: Send email -> Wait 3 days -> Send follow-up -> Wait 5 days -> Send final offer.

8. Settings - Managing Your Account

The Settings page displays your profile and lets you change your password.

7.1 Your Profile

Shows your name, email address, and role (Manager). This is read-only.

7.2 Changing Your Password

- Enter current password
- Enter new password (min 8 chars, must include uppercase, lowercase, and digit)
- Confirm new password
- Click "Change Password"

9. Notifications

Managers receive notifications for key events across the entire agency. The bell icon in the top bar shows your unread count.

- Click the bell to view notifications
- "Mark all read" clears all unread notifications
- Notifications poll automatically every 30 seconds

You receive notifications for:

- Leads assigned to reps
- Demo requests created, scheduled, or completed
- Handovers created or completed
- Deals closed by any rep

10. Technical Reference

9.1 System Architecture

The CRM consists of two main components:

- Backend: FastAPI (Python) hosted on PythonAnywhere
- Frontend: React (TypeScript) hosted on Cloudflare Pages
- Database: PostgreSQL (or SQLite for local development)

9.2 Deployment

The system uses GitHub Actions for CI/CD:

- Backend: Git push to PythonAnywhere, then run the reload script
- Frontend: Automatic deployment via Cloudflare Pages on push to main
- CI/CD pipeline: Tests run automatically before deployment

9.3 Backend Management (PythonAnywhere)

- Access: PythonAnywhere dashboard with your account credentials
- Code: Clone/pull from GitHub repository
- Environment variables: Configure in the PythonAnywhere web tab
- Restart: Use the reload button or the deployment script
- Database: Managed via SQLite file or external PostgreSQL connection

9.4 Environment Variables

The backend requires these environment variables:

- DATABASE_URL - Database connection string
- JWT_SECRET - Secret key for JWT token generation
- CORS_ORIGINS - Comma-separated list of allowed frontend origins
- JWT_EXPIRATION_HOURS - Token expiry time (default: 24)

9.5 Adding New Reps

To add a new sales rep to the system:

- Navigate to the Users page (sidebar -> Users)
- Click "Add User" and fill in their details with role = Sales Rep
- Provide them with the CRM URL and their credentials
- Assign leads to them from the Leads page

9.6 Adding New Managers

To add another manager or admin: Follow the same process as adding a user, but select the "Manager" role.

9.7 Password Policy

User passwords must:

- Be at least 8 characters long
- Contain at least one uppercase letter
- Contain at least one lowercase letter

- Contain at least one digit

9.8 Security Notes

- JWT tokens expire after 24 hours (users must log back in)
- Rate limiting: 10 requests per 60 seconds per IP
- Security headers: CSP, HSTS, X-Frame-Options are enforced
- Passwords are hashed using bcrypt
- Always use HTTPS in production

9.9 Troubleshooting

- User can't log in? Check if their account is active (Users page)
- Leads not showing up? Check filters and pagination
- Upload failing? Check file format (.csv/.xlsx/.xls) and size limit (10MB)
- API errors? Check the backend logs on PythonAnywhere
- Frontend issues? Check the browser console for errors

SUPPORT:

For technical issues, contact the system administrator or developer.