

ISE Boilerplate - Author Guide

Date: June 12, 2026

Adobe

Table of Contents

ISE Boilerplate - Author Guide	3
Quick Reference	3
Getting Started	3
Content Organization	4
Block Library	4
Available Blocks	5
Page Templates	6
Configuration Sheets	6
Publishing Workflow	6
Common Tasks	6
Sections and Section Metadata	6
Page Metadata	7
Images and Media	7
Troubleshooting	7
Resources	8
Support Contacts	8

ISE Boilerplate - Author Guide

This guide helps content authors and content managers create, edit, and publish content for the **ise-boilerplate** site. The project is built on AEM Edge Delivery Services and supports authoring with the **Universal Editor** as well as document-based authoring in Document Authoring (DA).

Quick Reference

Resource	URL
Document Authoring (DA)	https://da.live/#/aemdemos/ise-boilerplate/
Preview	https://main-ise-boilerplate-aemdemos.aem.page/
Live	https://main-ise-boilerplate-aemdemos.aem.live/
Block Library	https://da.live/#/aemdemos/ise-boilerplate/.da/library
Bulk Operations	https://da.live/apps/bulk

Sites

Site	Content Source (DA)	Preview	Live
ise-boilerplate	aemdemos/ise-boilerplate	https://main-ise-boilerplate-aemdemos.aem.page/	https://main-ise-boilerplate-aemdemos.aem.live/

Note: This site belongs to the shared **aemdemos** Config Service organization. The content path `aemdemos/ise-boilerplate` is taken from the site's content source (`content.da.live/aemdemos/ise-boilerplate/`) and is used to build the DA and Block Library URLs above.

Getting Started

Access Requirements

- ☐ DA access for the `aemdemos/ise-boilerplate` content path (request from your admin)
- ☐ An `@adobe.com` account — author and publish permissions are granted to `*@adobe.com`
- ☐ Preview / publish permissions (included with author access)

Admin contacts for access requests: chelms@adobe.com, dfink@adobe.com.

Your First Page

- Open DA: <https://da.live/#/aemdemos/ise-boilerplate/>
- Navigate to the correct folder for your content.
- Create a new document.
- Insert blocks from the **Library** sidebar (see Block Library below).

5. Add a **Metadata** block at the bottom of the page (title, description, etc.).
6. **Preview**, review, then **Publish**.

Tip: This project also supports the **Universal Editor (Canvas)**. The Sidekick exposes a "Canvas" plugin so you can edit pages visually in addition to document authoring.

Content Organization

Site Structure

Content lives under the `aemdemo/ise-boilerplate` path in DA. Pages are composed of **sections**, and each section contains default content (text, headings, images, links) and **blocks**. Use horizontal rules (---) to separate sections within a document.

Navigation and Footer

Navigation and footer are content-driven and edited in DA:

Element	Where to edit
Navigation	The nav document in DA
Footer	The footer document in DA

Edit these documents, then Preview and Publish to update the header/footer across the site.

Languages

This project is configured as a single-language site. No additional language folders are defined. If localization is added later, language content typically lives in language-prefixed folders (e.g. `/en`, `/fr`) and reusable strings are managed via the Placeholders sheet.

Block Library

The **Block Library** is the sidebar in Document Authoring where you browse and insert blocks into your document.

What	Details
Open in DA	Use the Library icon in the DA editor sidebar, or open the Block Library URL directly: https://da.live/#/aemdemo/ise-boilerplate/.da/library
What's in it	The blocks listed in "Available Blocks" below
How to use	Click a block in the library to insert it at the cursor position in your document

When creating or editing a page, use the Library sidebar to add blocks instead of typing block names manually. In the Universal Editor, use the component picker, which is filtered to the blocks allowed in each section.

Available Blocks

Block	Purpose	Variants	Usage
accordion	Collapsible question/answer or expandable content panels	—	FAQs, expandable details where space is limited
card	A single card (image, title, text, link); used inside cards and card-carousel	—	Building block for card layouts
cards	A grid of cards	—	Feature lists, product/article tiles, link collections
card-carousel	A horizontally scrolling set of cards	—	Showcasing multiple cards in limited space
carousel	A rotating slideshow of content slides	—	Hero rotators, featured content galleries
columns	Multi-column side-by-side layout of text and images	—	Comparisons, paired text/image layouts
embed	Embeds external content (e.g. social, third-party)	embed-twitter	Embedding videos, posts, or external widgets
form	Renders a form from a form definition	—	Contact, signup, and data-capture forms
fragment	Reuses content from another document	—	Shared content (banners, promos) across pages
hero	Large banner with background image, heading, and call to action	—	Page headers, landing-page banners
modal	Pop-up dialog content	—	Overlays, alerts, gated content prompts
quote	Styled blockquote / testimonial	—	Testimonials, pull quotes, citations
search	On-page search experience	minimal	Search results pages, in-page search
section-title	Styled section heading with alignment, size, and color options	center, left, right; size-xs/s/m/l/xl/xxl; subtitle-size-xs/s/m/l/xl/xxl; color-text/dark/light/link/background	Section headers and titles with fine-grained styling
table	Tabular data	block	Specifications, schedules, comparison tables
tabs	Tabbed content panels	—	Grouping related content under selectable tabs
video	Embedded video player	—	Hosted video playback

The **section-title** block exposes alignment (`center`, `left`, `right`), title sizes (`size-xs` through `size-xxl`), subtitle sizes, and color treatments. Apply these as block variants/options.

Page Templates

This project does not define named page templates in code. Pages are composed freely from sections and blocks. Page-level styling and behavior are controlled through **Section Metadata** (section styles) and the **Metadata** block (page properties) rather than a template value.

Configuration Sheets

Configuration sheets are managed in DA (no local sheet files are committed to this repo). Create/edit them at the corresponding DA path, then Publish.

Sheet	Location	Purpose	When to Update
Placeholders	/placeholders in DA	Reusable text strings and translations	Changing labels, button text, configurable copy
Redirects	/redirects in DA	Forward old URLs to new URLs	After deleting, moving, or renaming pages
Bulk Metadata	/metadata in DA	Apply metadata to many pages via URL patterns	Setting default metadata by folder/section

Publishing Workflow

Environment	Domain	Purpose
Preview	https://main-ise-boilerplate-aemdemos.aem.page/	Test changes before going live
Live	https://main-ise-boilerplate-aemdemos.aem.live/	Production site

Workflow: Edit in DA (or Universal Editor) → **Preview** → review → **Publish** → Live immediately.

Bulk preview/publish: <https://da.live/apps/bulk>

Common Tasks

Task	Steps
Create a Page	Navigate to folder → New → Document → Add content/blocks → Add Metadata → Preview → Publish
Edit a Page	Open in DA (or Canvas/Universal Editor) → Make changes → Preview → Publish
Delete a Page	Add a redirect first → Delete document → Publish the redirects sheet
Update Navigation	Edit the nav document → Preview → Publish
Update Footer	Edit the footer document → Preview → Publish

Sections and Section Metadata

Sections group content together. Create sections by separating content with horizontal rules (---).

Add **styles** with a Section Metadata block at the end of a section:

Section Metadata	
style	[style-name]

Available Section Styles:

Style	Effect
light	Light background treatment for the section
highlight	Highlighted background treatment to draw attention to the section

Page Metadata

Add a **Metadata** block at the bottom of each page:

Property	Required	Purpose	Example
title	Yes	Page title for SEO and browser tab	"About Us"
description	Yes	SEO and social description	"Learn about our team..."
image	No	Social sharing (Open Graph) image	/images/og.jpg
keywords	No	Comma-separated SEO key-words	"boilerplate, demo"

Images and Media

Method	How
Drag & drop	Drag images directly into the DA editor
AEM Assets	Use the Assets sidebar in DA to pick managed assets

Best Practices:

- Use descriptive filenames.
- Always add meaningful alt text (use empty alt only for purely decorative images).
- Author-uploaded images are automatically optimized.

Troubleshooting

Issue	Solution
Page not updating after publish	Wait 1–2 minutes for cache, then hard refresh (Cmd/Ctrl+Shift+R)
Block not displaying correctly	Check the block structure matches the expected format; verify the variant/option spelling
Images not showing	Verify the image was uploaded to DA and the path is correct

Issue	Solution
Section style not applied	Confirm the Section Metadata style value is light or highlight and is at the end of the section
Navigation/footer not updating	Re-publish the nav / footer document

Resources

Resource	URL
DA Documentation	https://docs.da.live/
Authoring Guide	https://www.aem.live/docs/authoring
Universal Editor Authoring	https://www.aem.live/docs/ue-authoring
Placeholders Docs	https://www.aem.live/docs/placeholders
Redirects Docs	https://www.aem.live/docs/redirects

Support Contacts

Role	Contact
Site admins	chelms@adobe.com , dfink@adobe.com
Authoring access	Any @adobe . com account has author/publish permissions