

#### PC Freezes When Idle: Causes & How to Prevent It

System file corruption is often the cause of this problem





- If your PC freezes when idle, it might be due to outdated graphics drivers on your PC.
- Whenever you encounter this problem, try to restart or force shut down your PC if nothing else works.
- You should also try to change your screen resolution settings to a lower option.

We all have, one way or the other, experienced a computer freezing problem before and know how that can be annoying sometimes. Some of our readers have recently reported that their PC freezes when idle too.

Fortunately, we have gathered some potential causes of this error and fixes to apply whenever your PC gets frozen when it was idle.

**≣** In this article >

# Why does my PC freeze when idle?

You need to know what is wrong if you were using your PC, but you had to leave it to attend to something else while your PC remains idle, but upon your return, your PC is frozen. Below are some of the factors responsible for this error:



or using resource-intensive apps. If you are using Windows 11 and a GPU that is not capable of handling the resolution you are trying to enforce, your PC may end up frozen when idle.

- **Outdated Graphics Driver** If you are still using outdated GPU Drivers, it can cause your PC to freeze due to incompatibility issues. The best thing to do here is to update your GPU drivers.
- Limited system VRAM Your PC can also freeze when idle if you have insufficient system RAM. In this case, extending virtual memory allocation can resolve such issues.
- **System file corruption** At times, if your PC freezes when idle, it might be due to corrupt or broken system files. You can use the built-in tools or dedicated software to repair and restore these files.

Since you now know some of the possible reasons why the PC freezes when idle, let us proceed to how you can fix this problem.

# What can I do when my PC freezes when idle?

Before trying any of the advanced solutions below, whenever your PC gets frozen when it is idle, try to perform the following preliminary checks:

- Inspect your hardware for possible issues.
- Make sure the graphics card you're using is a dedicated one.
- Disconnect all USB cables and peripheral devices.
- Try to restart or force shut down your PC.

Having confirmed the above checks, and none of them fixes the issue, you can explore the advanced solutions provided below.






## 1. Change your System's Sleep Mode settings

- 1. Press the **Start** button on your *Taskbar*, type **Control Panel**, and launch it.
- 2. Set your *View by* to **Large icon** in the control panel and click on *Power Options*.





3. Then, select **Edit Power Settings** and click on the *Change plan settings* option.



	Control Panel Home	Choose or customize a power plan
	Choose what the power button does	A power plan is a collection of hardware and system settings (like display brightness, sleep, etc.) that manages how your computer uses power. <u>Tell me more about power plans</u>
	Choose what closing the lid does	Plans shown on the battery meter
	Create a power plan	HP Recommended Change plan settings Automatically balances performance with energy consumption on capable hardware.
	Choose when to turn off the display	,
•	Change when the computer sleeps	Show additional plans

See also


- 4. Select the **Change advanced power settings** option.
- 5. Navigate to *Sleep*, then click **Hibernate after** the menu item and change its value to *Never* for both **On-battery and Plugged-in** options.
- 6. Click on *Apply* and **OK** to save the changes and close the windows.

Although this is not a permanent solution, adjusting your system's sleep mode should help you keep your PC active when it's not in use, hence making it less idle.


### 2. Change your system's resolution settings

- 1. Press the Windows + I keys to open the **Settings** app.
- 2. Navigate to the *System* tab and choose the **Display** option.
- 3. Then, click on the *Display resolution* option to view the multiple resolutions to choose from.





4. Choose a resolution that is lower than the current one.




5. Finally, click the **Keep changes** option on the dialog box prompt to save the changes.

It is worth noting that Windows 11 has different hardware requirements than earlier versions and this may sometimes trigger hardware issues.


Also, your screen resolution may be too high for your graphics adapter, so, try a few different resolutions to see if any of them solve the freezing problem.



1. Press the Windows, type Windows Memory Diagnostic in the search box, and launch it.







3. Once Windows restarts, Windows Memory Diagnostic should do a scan and then provide the results.

By running this test, you'll be able to detect any errors with your VRAM. Alternatively, you can use the Event Viewer to check the scan result in our detailed guide on Memory Diagnostic Tool mdsched.exe.

#### Read more about this topic

- 4 Ways to Fix WD External Hard Drive not Showing Up
- Can't Block Sites on Netgear? Here's What to do
- Windows Mail Error Code 0x80040b0b: 6 Ways to Fix it
- 9 Ways to Fix IPv6 No Internet Access

#### 4. Update your Graphics driver




2. Double-click on **Display adapters**, right-click on the *graphics driver* and select **Update driver** from the context menu.



3. Now, select *Search automatically for drivers* and let Windows install the best available version.





4. Restart your computer after the updating process is complete.


To be on the safe side, update all your graphics drivers. However, you can visit the manufacturer's website for dedicated display drivers such as Intel, AMD, or Nyidia.

If you're concerned about picking the incorrect versions for your drivers, you can use a dedicated tool, such as Outbyte Driver Updater, to automatically get the right and latest driver options.

### 5. Perform a Clean Boot

- 1. Press the Windows + R keys to open the **Run** command dialog, type *msconfig* in the text field and press Enter to open the **System Configuration** window.
- 2. Navigate to the *Services* tab, check the box next to **Hide all Microsoft services**, and click on *Disable all*.





3. Next, navigate to the **Startup** tab and click on *Open Task Manager* below.



- 5. Go back to the *System Configuration* window and click on **Apply**, then click on *OK*.
- 6. Finally, restart your PC.

To detect the cause of the problem, perform a clean-boot troubleshoot, follow the steps above, and then restart the computer after each action. Once you have identified the culprit, you can consider removing or disabling it.

Try to work your way through the steps provided in this article one after the other to know what fixes the problem.

Similarly, you can explore our dedicated guide on thorough solutions to apply if Windows 11 is not responding or is frozen for further information on how to fix the issue.



## Still experiencing troubles? Fix them with this tool:

**SPONSORED** 

Some driver-related issues can be solved faster by using a tailored driver solution. If you're still having problems with your drivers, simply install **OutByte Driver Updater** and get it up and running immediately. Thus, let it update all drivers and fix other PC issues in no time!