

Getting Started with the NGC CLI

Go to <https://ngc.nvidia.com/setup/installers/cli> to download the CLI and to read the installation instructions for your platform.

After you install the CLI, your first step is to configure the CLI for your NGC account.

Configuring NGC CLI

The first time that you use the CLI, you must set your configuration. To set your configuration, run the following command and follow the prompts.



Tip

You will need your API key. For information about generating an API key, refer to the preceding link.

```
ngc config set
```

Tracing

You can disable tracing when encountering errors with proxy or other settings.

The following environment variable disables tracing:

`NGC_CLI_TRACE_DISABLE`

Specify to disable tracing.

About the Output Format

The following output blocks are examples of the `ascii`, `csv`, and `json` CLI output format. The examples show the response to the `ngc user who` command.

ASCII

```
+-----+-----+-----+-----+
| User Id | Name           | Email               | Created Date           |
+-----+-----+-----+-----+
| 169     | John Smith    | jsmith@example.com | 2017-08-23 04:04:58 UTC +0 |
+-----+-----+-----+-----+
```

CSV

```
169,John Smith,jsmith@example.com,2017-08-23 04:04:58 UTC +0
```

JSON

```
{
  "createdDate": "2017-08-23T04:04:58.000Z",
  "email": "jsmith@example.com",
  "hasSignedEULA": false,
  "id": 169,
  "isActive": true,
  "isDeleted": false,
  "isSAML": true,
  "name": "John Smith"
}
```

Setting Your Configuration

NGC CLI configuration ensures that you have access to the resources and roles for an organization. The configuration also determines which container registry space within your organization that you can access.

When you configure the NGC CLI for the first time, you set the default organization to associate with your user name. If you use only the resources that are associated with your organization, then no other action is necessary.

However, to use resources and container registry spaces associated with other organizations or teams of which you are a member, you must change your configuration accordingly.

The following code block shows the named arguments for the `ngc config set` command that set your organization, team, and so on.

```
ngc config set [--org org-name] [--team team-name] [--format_type fmt]
```



Tip

The organization name must be specified for all configurations.

For more information, see the syntax for the [ngc config set](#) command.

Using the CLI

To run a CLI command, enter `ngc` followed by a command name, such as `config`, and the required and optional arguments for the command.

Refer to the commands reference section of this document to learn about the commands and the arguments for each command.

You can enter `-h` for any command to learn the required and optional arguments for the command.

View the help for the ngc command

```
ngc -h
```

Example Output

```
usage: ngc [--debug] [--format_type <fmt>] [--org <name>] [--team <name>] [--version] [-h]
        {alert,audit,cloud-function,config,diag,fleet-command,forge,org,registry,team,version}

NVIDIA NGC CLI

optional arguments:
  -h, --help            Show this help message and exit.
  --debug              Enable debug mode.
  --format_type <fmt> Specify the output format type. Supported formats are: ascii, csv, json,
                        format. Default: ascii
  --org <name>         Specify the organization name. Use "--org no-org" to override other sources.
  --team <name>        Specify the team name. Use "--team no-team" to override other sources.
  --version            Show the CLI version and exit.

ngc:
  {alert,audit,cloud-function,config,diag,fleet-command,forge,org,registry,team,user,version}
  alert                Alert Commands
  audit                Audit Commands
  cloud-function        Cloud Function Commands
  config                Configuration Commands
  diag                 Diagnostic Commands
  fleet-command         Fleet Command Commands
  forge                 Forge Commands
  org                   Org Commands
  registry              Registry Commands
  team                  Team Commands
  user                  User Commands
  version               Version Commands
```

View the help for the ngc config command

```
ngc config -h
```

Example Output

```
usage: ngc config [--debug] [--format_type <fmt>] [--org <name>] [--team <name>] [-h] {c]
```

Configuration Commands

optional arguments:

-h, --help	Show this help message and exit.
--debug	Enable debug mode.
--format_type <fmt>	Specify the output format type. Supported formats are: ascii, csv
--org <name>	Specify the organization name. Use " --org no-org " to override oth
	current configuration
--team <name>	Specify the team name. Use " --team no-team " to override other sou

config:

{clear,clear-cache,current,set}	
clear	Clear the configuration stored in the user settings file.
clear-cache	Clear cached values.
current	List the current configuration.
set	Set the configuration in the user settings file. Use optional arg



[Privacy Policy](#) | [Your Privacy Choices](#) | [Terms of Service](#) | [Accessibility](#) | [Corporate Policies](#) | [Product Security](#) | [Contact](#)

Copyright © 2018-2026, NVIDIA Corporation.