

config

Configuration Commands

```
usage: ngc config [--debug] [--format_type <fmt>] [--org <name>]
                [--team <name>] [-h]
                {clear,clear-cache,current,set} ...
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

config

{clear,clear-cache,current,set}

Possible choices: clear, clear-cache, current, set

Sub-commands

clear

Clear the configuration stored in the user settings file.

```
ngc config clear [--debug] [--format_type <fmt>] [--org <name>]
                [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

clear-cache

Clear cached values.

```
ngc config clear-cache [--debug] [--format_type <fmt>] [--org <name>]
                      [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

set

Set the configuration in the user settings file. Use optional arguments to choose what will be set.

```
ngc config set [--auth-option {api-key,email}] [--debug] [--format_type <fmt>]
               [--org <name>] [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--auth-option

Possible choices: api-key, email

Specify authentication option ('api key' or 'email') for setting config.

current

List the current configuration.

```
ngc config current [--debug] [--format_type <fmt>] [--org <name>]
                  [--show-auth-token] [--team <name>] [--yes] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--show-auth-token

Show the Docker login password (Starfleet ID Token) if this flag is set.

--yes

Automatically confirm the retrieval of the auth token without prompting.

Examples

How to set config?

```
$ ngc config set --format_type json
```

```
Successfully saved NGC configuration C:\Users\<username>\.ngc\config
```

```
$ ngc config set
```

```
Enter API key[*****]
Enter CLI output format type [ascii]. Choices: ['ascii', 'csv', 'json']
Enter default org [b0xlotzw8zo9]. Choices: [b0xlotzw8zo9, nvidia]:
Successfully saved NGC configuration C:\Users\foo\.ngc\config
```



[Privacy Policy](#) | [Your Privacy Choices](#) | [Terms of Service](#) | [Accessibility](#) | [Corporate Policies](#) | [Product Security](#) | [Contact](#)

Copyright © 2018-2026, NVIDIA Corporation.