

org

Org Commands

```
usage: ngc org [--debug] [--format_type <fmt>] [--org <name>] [--team <name>]
              [-h]
              ...
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

org



Possible choices: add-team, add-user, delete-invitation, info, list, list-users, remove-team, remove-user, update-team, update-user, user-group

Sub-commands

user-group

External User Group Commands

```
ngc org user-group [--debug] [--format_type <fmt>] [--org <name>]
                  [--team <name>] [-h]
                  ...
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

user-group



Possible choices: add-member, create, delete, info, list, remove-member, resend-invite, revoke-access, revoke-invite, send-invite, suspend, update, update-permissions

Sub-commands

list

List external user groups in an org.

```
ngc org user-group list [--debug] [--format_type <fmt>] [--org <name>]
                        [--team <name>] [--type <type>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--type

Filter by group type. Values: USER_GROUP, DELEGATED_USER_GROUP, DELEGATED_USER_GROUP_INVITATION (pending delegated EUG invitations).

info

Get details of a specific external user group.

```
ngc org user-group info [--debug] [--format_type <fmt>] [--org <name>]
                        [--team <name>] [-h]
                        <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

create

Create a managed external user group. Org Admin only.

```
ngc org user-group create [--debug] [--description <text>]
                        [--format_type <fmt>] --name <name> [--org <name>]
                        [--resource-group <name>] --service-roles <roles>
                        [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--resource-group

Resource group (team) to associate with the user group.

--description

Group description (max 512 chars).

Required named arguments

--service-roles

Comma-separated NGC service roles to grant (e.g. REGISTRY_READ,CATALOG_READ). Required.

--name

Group name (3-64 chars, required).

delete

Delete a managed external user group. Org Admin only.

```
ngc org user-group delete [--debug] [--format_type <fmt>] [--org <name>]
                           [--team <name>] [-h]
                           <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

update

Update a managed external user group. Org Admin only.

```
ngc org user-group update [--debug] [--description <text>]
                        [--format_type <fmt>] [--name <name>] [--org <name>]
                        [--resource-group <name>] [--service-roles <roles>]
                        [--team <name>] [-h]
                        <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--resource-group

Updated resource group (team) name.

--service-roles

Updated comma-separated NGC service roles.

--description

Updated group description.

--name

Updated group name (3-64 chars).

add-member

Invite one or more external users to a managed external user group by email. Org Admin only.

```
ngc org user-group add-member [--debug] --email <email>
                                [--email-message <text>]
                                [--email-subject <text>] [--format_type <fmt>]
                                [--invitation-expiry <minutes>] [--org <name>]
                                [--role <role>] [--team <name>] [-h]
                                <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--email-message

Override invitation email body (max 5000 chars). Only for --role MEMBER; ignored for ADMIN/OPERATOR.

--email-subject

Override invitation email subject. Only applies when --role MEMBER; ignored for ADMIN and OPERATOR.

--invitation-expiry

Invitation expiry in minutes (0-43200, max 30 days).

--role

Role to assign to invited users. Values: ADMIN, OPERATOR, MEMBER (default: MEMBER).

Required named arguments

--email

External user email address. Repeat for multiple users.

remove-member

Remove a user from a managed external user group. Org Admin only.

```
ngc org user-group remove-member [--debug] [--format_type <fmt>]
                                   [--org <name>] [--team <name>] --user-id
                                   <user-id> [-h]
                                   <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

Required named arguments

--user-id

ID of the user to remove.

send-invite

Send an invitation to a Resource Org Admin to accept a delegated EUG. NCP Admin only.

```
ngc org user-group send-invite [--debug] [--description <text>] --email
                                <email> [--email-message <text>]
                                [--email-subject <text>] [--format_type <fmt>]
                                --group-name <name> --invitation-expiry
                                <minutes> [--org <name>]
                                [--resource-group <name>] --service-roles
                                <roles> [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--email-message

Override invitation email body (max 5000 chars).

--email-subject

Override invitation email subject.

--resource-group

Resource group (team) to associate with the delegated EUG.

--description

Group description.

Required named arguments

--service-roles

Comma-separated NGC service roles to grant. Required.

--invitation-expiry

Invitation expiry in minutes (0-43200, max 30 days). Required.

--email

Email of the Resource Org Admin to invite. Required.

--group-name

Name of the delegated EUG to create (3-64 chars). Required.

revoke-invite

Revoke a pending delegated EUG invitation. NCP Admin only.

```
ngc org user-group revoke-invite [--debug] [--format_type <fmt>]
                                [--org <name>] [--team <name>] [-h]
                                <invitation-id>
```

Positional Arguments

<invitation-id>

Invitation ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team.
Default: current configuration

resend-invite

Resend a pending delegated EUG invitation. NCP Admin only.

```
ngc org user-group resend-invite [--debug] [--email-message <text>]
                                [--format_type <fmt>] [--org <name>]
                                [--team <name>] [-h]
                                <invitation-id>
```

Positional Arguments

<invitation-id>

Invitation ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team.
Default: current configuration

--email-message

Override invitation email body (max 5000 chars).

update-permissions

Update service roles and permissions granted to a delegated EUG. Resource Org Admin only.

```
ngc org user-group update-permissions [--debug] [--description <text>]
                                     [--format_type <fmt>] [--org <name>]
                                     [--resource-group <name>]
                                     --service-roles <roles> [--team <name>]
                                     [-h]
                                     <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--resource-group

Updated resource group (team) name.

--description

Updated group description.

Required named arguments

--service-roles

Updated comma-separated NGC service roles to grant. Required.

suspend

Suspend all access for a delegated EUG by removing all service roles. Resource Org Admin only.

```
ngc org user-group suspend [--debug] [--format_type <fmt>] [--org <name>]
                             [--team <name>] [-h]
                             <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

revoke-access

Permanently remove a delegated EUG's access from the resource org. Resource Org Admin only.

```
ngc org user-group revoke-access [--debug] [--format_type <fmt>]
                                   [--org <name>] [--team <name>] [-h]
                                   <group-id>
```

Positional Arguments

<group-id>

User Group ID (if ID starts with '-', use '--' separator, e.g. -- -abc)

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

list

List all accessible organizations.

```
ngc org list [--column <column>] [--debug] [--format_type <fmt>]
              [--org <name>] [--team <name>] [-h]
```

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team.
Default: current configuration

--column

Specify output column as column[=header], header is optional, default is id[=Id]. Valid columns are id[=Id], name[=Name], displayName[="Display Name"], description[=Description], type[=Type], ncaAccountNumber[="Cloud Account Number"], billingAccountId[="Cloud Account ID"]. Use quotes with spaces. Multiple column arguments are allowed.

info

Get organization details.

```
ngc org info [--debug] [--format_type <fmt>] [--org <name>] [--team <name>]
              [-h]
              <org_name>
```

Positional Arguments

<org_name>

Organization name

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team.
Default: current configuration

add-user

(For administrators only) Add (create) a user to the current organization.

```
ngc org add-user [--debug] [--format_type <fmt>]
                 [--invitation-expiry <duration>] [--message <text>] [--name]
                 [--org <name>] --role <r> [--team <name>] [-h]
                 <email>
```

Positional Arguments

<email>

User Email

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--name

[DEPRECATED] This parameter is not used and will be ignored.

--invitation-expiry

Invitation expiry duration. Options: '1 hour', '6 hours', '24 hours', '1 week', '1 month'. IMPORTANT: Multi-word values must be quoted! Example: --invitation-expiry '1 week'. Default: '24 hours'

--message

Custom invitation message to include in the email. If not provided, uses default message.

Required named arguments

--role

Specify the user role. Options: FLEET_COMMAND_ADMIN, FLEET_COMMAND_OPERATOR, FLEET_COMMAND_VIEWER, NVIDIA_AI_ENTERPRISE_VIEWER, OMNIVERSE_ADMIN, OMNIVERSE_READ, OMNIVERSE_USER, ORG_OWNER, REGISTRY_ADMIN, REGISTRY_READ, REGISTRY_USER, USER_ADMIN. To specify more than one role, use multiple --role arguments. NOTE: NVIDIA Cloud Account role (Member/Admin) is automatically determined based on NGC role.

update-user

(For administrators only) Update a user's roles in the current organization.

```
ngc org update-user [--add-role <add_role>] [--debug] [--format_type <fmt>]
                    [--org <name>] [--remove-role <remove_role>]
                    [--role <role>] [--team <name>] [-h]
                    <id>
```

Positional Arguments

<id>

User ID

Named Arguments

--debug

Enable debug mode.

--format_type

Possible choices: ascii, csv, json

Specify the output format type. Supported formats are: ['ascii', 'csv', 'json']. Only commands that produce tabular data support csv format. Default: ascii

--org

Specify the organization name. Use "--org no-org" to override other sources and specify no org (no-org cannot be used if API key is set). Default: current configuration

--team

Specify the team name. Use "--team no-team" to override other sources and specify no team. Default: current configuration

--role

Replace all existing user roles with the specified role(s). This will remove any roles not specified. Options: FLEET_COMMAND_ADMIN, FLEET_COMMAND_OPERATOR, FLEET_COMMAND_VIEWER, NVIDIA_AI_ENTERPRISE_VIEWER, OMNIVERSE_ADMIN, OMNIVERSE_READ, OMNIVERSE_USER, ORG_OWNER, REGISTRY_ADMIN, REGISTRY_READ, REGISTRY_USER, USER_ADMIN. To specify more than one role, use multiple --role arguments.

--add-role

Specify the user role to assign. Options: [FLEET_COMMAND_ADMIN, FLEET_COMMAND_OPERATOR, FLEET_COMMAND_VIEWER, NVIDIA_AI_ENTERPRISE_VIEWER, OMNIVERSE_ADMIN, OMNIVERSE_READ, OMNIVERSE_USER, ORG_OWNER, REGISTRY_ADMIN, REGISTRY_READ, REGISTRY_USER, USER_ADMIN]. To specify more than one role, use multiple --add-role arguments.

--remove-role

Specify the user role to remove. Options: [FLEET_COMMAND_ADMIN, FLEET_COMMAND_OPERATOR, FLEET_COMMAND_VIEWER, NVIDIA_AI_ENTERPRISE_VIEWER, OMNIVERSE_ADMIN, OMNIVERSE_READ, OMNIVERSE_USER, ORG_OWNER, REGISTRY_ADMIN, REGISTRY_READ, REGISTRY_USER, USER_ADMIN]. To specify more than one role, use multiple --remove-role arguments.