

How to Connect to Your Hosting Using FTP in Hostinger

 hostinger.com/support/4480505-how-to-connect-to-your-hosting-using-ftp-in-hostinger

migration

September 25, 2020

FTP Access		
FTP IP (hostname)	1	ftp://185.185.185.185 
FTP username	2	u12345678 
FTP port	3	21
Folder to upload files		public_html
Forgot your FTP password?		Change FTP password
Recommended FTP clients		SmartFTP or FileZilla

For websites built using file-based systems—such as WordPress, Joomla, or custom HTML—you can manage and transfer data using an FTP connection. This feature is available on Hostinger web, cloud, and Agency hosting plans and allows you to move large amounts of data between your local computer and your account efficiently.

FTP access is not supported for websites created with Hostinger Website Builder or Hostinger Horizons, as these platforms do not allow external file transfers.

Step 1 – Preparations

First, make sure that:

- An FTP client is installed on your device; we recommend [FileZilla](#)(client version).
- You have your website's [FTP information](#) ready. You can find it by navigating to **Websites** → **Dashboard**, searching for **FTP Accounts** in the sidebar, and clicking on it.

If you need to create or reset your FTP password, refer to this guide: [How to change your FTP password on hPanel](#).

Step 2 – Connection


Using FileZilla as an example, you have two main options to establish a connection.

Option 1 – Direct Access

Open FileZilla and fill in the Quickconnect section with the FTP details you got from the **FTP Accounts** section:

FTP Access		
FTP IP (hostname)	1	ftp://185.185.185.185 
FTP username	2	u12345678 
FTP port	3	21
Folder to upload files		public_html
Forgot your FTP password?		Change FTP password
Recommended FTP clients		SmartFTP or FileZilla


1. **Host:** The FTP IP
2. **User:** Your FTP username
3. **Port:** 21



The image shows the FileZilla Quickconnect interface. It includes a menu bar (File, Edit, View, Transfer, Server, Bookmarks, Help) and a toolbar with various icons. Below the toolbar, there are input fields for Host, Username, Password, and Port, followed by a Quickconnect button. Red numbers 1, 2, and 3 are placed below the Host, Username, and Port fields respectively to indicate the fields to be filled.

Host:	ftp://185.185.185.185	Username:	u123456789	Password:	••••••••	Port:	21	Quickconnect
	1		2				3	

Enter your FTP account password in the corresponding field and click **Quickconnect**. The first time you connect to a server, you may encounter an Unknown certificate message. To proceed, check the **Always trust this certificate in future sessions** option and click **OK**:




If successfully connected, you will get a **Status: Logged in** message in the area below the Quickconnect bar.


Option 2 – Site Manager

With **Site Manager**, you can save your connection details, adjust the encryption type, or the protocol (FTP or [SFTP](#)).


1. Open **Site Manager** in FileZilla:



2. Click on **New site**:



Then, configure the settings as follows, using the information from the **FTP Accounts** section:



- **Protocol:** Select **FTP – File Transfer Protocol** from the dropdown.
- **Host:** The FTP IP
- **Port:** 21

- **Encryption:** Select **Only use plain FTP**
- **Logon type:** Normal
- **User:** FTP username
- **Password:** Your FTP password

Click on **Connect**, and if the details entered are correct, a **Status: Logged in** message will confirm the connection.

For more information on navigating the FileZilla interface to upload and download files, refer to this tutorial: [How to use FileZilla](#).

NOTE

The FTP feature is enabled by default on web, cloud, and Agency hosting plans. This setting is fixed and cannot be changed, except on VPS plans.

© 2004-2026 Hostinger – Launch, grow, and succeed online, supported by AI that puts the power in your hands.

Prices are listed without VAT