

How to Connect to Your Hosting Using SFTP in Hostinger

 hostinger.com/support/5972689-how-to-connect-to-your-hosting-using-sftp-in-hostinger

migration

February 11, 2022

SFTP is available on all hosting plans which have SSH access included, that is, [Premium](#) and above. Just follow these steps:

Step 1 – Preparations

First, make sure that:

- You have [enabled SSH access](#).
- You have installed the client version of [FileZilla](#) on your device

Step 2 – Connecting

You can easily connect to SFTP by following one of the options below:

Option 1 – Direct Access

Open **FileZilla** and fill in the Quickconnect section with the configuration you got from the **SSH Access** section:

- **Host:** FTP IP from SSH Access section
- **User:** FTP/SSH Username
- **Port:** 65002

SSH Access

🏠 - Hosting - domain.tld - Advanced - SSH Access

SSH details

IP	1	185.185.185.185	📄
Port	2	65002	📄
Username	3	u123456789	📄
Password		Change	

FileZilla

File Edit View Transfer Server Bookmarks Help

Host: sftp://185.185.185.1 Username: u123456789 Password: Port: 65002 [Quickconnect](#) ▼

1 3 2

Click on **Quickconnect** – and you will be connected to FTP server 😊

If you encounter an Unknown host key message, check Always trust this host and click OK:

Unknown host key

i The server's host key is unknown. You have no guarantee that the server is the computer you think it is.

Details

Host: 185.185.185.185:65002
Hostkey algorithm: ssh-ed25519
Fingerprints: SHA256:ZQw/t5k+ ZQw/t5kYRZQw/t5k-ZQw/t5ZQw/t5ZQw/t5k

Trust this host and carry on connecting?


☒ Always trust this host, add this key to the cache

[OK](#) [Cancel](#)


Option 2 – Site Manager

Unlike Direct access, with Site Manager, you are able to save your previous connection details, as well as change the encryption type.


Open **Site Manager** in FileZilla:



Click **New Site**:



Select **SFTP** connection:



Set the configuration you got from **SSH Access or Remote Access** section:

- **Protocol:** SFTP – SSH File Transfer Protocol
- **Host:** FTP IP from the FTP Accounts section (for example, 185.185.185.185)
- **Port:** 65002
- **Logon type:** Normal
- **User:** FTP/SSH Username

FileZilla

The image shows two side-by-side screenshots. The left screenshot is from a web hosting control panel's 'SSH Access' section. It lists details for an SSH connection: IP (185.185.185.185), Port (65002), Username (u123456789), and a Password field with a 'Change' link. Red numbers 1, 2, and 3 are placed next to the IP, Port, and Username respectively. The right screenshot is the FileZilla client's 'General' tab dialog box. It shows the 'Protocol' set to 'SFTP - SSH File Transfer Protocol', 'Host' as '185.185.185.185', 'Port' as '65002', 'Logon Type' as 'Normal', and 'User' as 'u123456789'. Red numbers 1, 2, and 3 are placed next to the Host, Port, and User fields respectively. A red arrow points from the number 2 to the Port field.

SSH details	
IP	185.185.185.185
Port	65002
Username	u123456789
Password	Change

FileZilla General tab fields:

- Protocol: SFTP - SSH File Transfer Protocol
- Host: 185.185.185.185
- Port: 65002
- Logon Type: Normal
- User: u123456789
- Password: [Empty]
- Background color: None
- Comments: [Empty]

Buttons: [Connect](#) [OK](#) [Cancel](#)

Click on **Connect** – and you will be connected to the server 😊

NOTE

The SFTP/SSH password is the same as the FTP password of your main domain. If you are not sure about the exact value, you can [set a new password](#) for both **FTP** and **SSH** or create an [SSH-only password](#)

© 2004-2026 Hostinger – Launch, grow, and succeed online, supported by AI that puts the power in your hands.

Prices are listed without VAT