


Default Gateway


Assign IP Address in router

A screenshot of a terminal window titled "Router" showing the configuration of a router. The terminal displays the configuration of two Ethernet interfaces, 0/0 and 0/1, with IP addresses 50.0.0.1 and 60.0.0.1 respectively. It also shows the status of the interfaces and a summary of the configuration.

```
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#
*Aug 21 06:50:55.318: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
Router(config)#interface ethernet 0/0
Router(config-if)#ip address 50.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#interface ethernet 0/1
Router(config-if)#ip address 60.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#exit
Router#
*Aug 21 06:55:50.765: %SYS-5-CONFIG_I: Configured from console by console
Router#show ip interface brief
```

Interface	IP-Address	OK?	Method	Status	Protocol
Ethernet0/0	50.0.0.1	YES	manual	up	up
Ethernet0/1	60.0.0.1	YES	manual	up	up
Ethernet0/2	unassigned	YES	TFTP	down	down

Assign IP Address and Subnet mask in two Pc's



Ping from both the pc

```
C:\WINDOWS\system32\cmd.exe

C:\Documents and Settings\user>route add 60.0.0.0 mask 255.0.0.0 50.0.0.1
C:\Documents and Settings\user>route print
=====
Interface List
0x1 ..... MS TCP Loopback interface
0x2 ..50 fe 9c 09 4f 00 ..... Intel(R) PRO/1000 MT Network Connection - Packet
Scheduler Miniport
=====
Active Routes:
Network Destination    Netmask          Gateway         Interface    Metric
50.0.0.0                255.0.0.0        50.0.0.10      50.0.0.10    10
50.0.0.10              255.255.255.255  127.0.0.1      127.0.0.1    10
50.255.255.255         255.255.255.255  50.0.0.10      50.0.0.10    10
60.0.0.0                255.0.0.0        50.0.0.1       50.0.0.10    1
127.0.0.0              255.0.0.0        127.0.0.1      127.0.0.1    1
224.0.0.0              240.0.0.0        50.0.0.10      50.0.0.10    10
255.255.255.255        255.255.255.255  50.0.0.10      50.0.0.10    1
=====
Persistent Routes:
None

C:\Documents and Settings\user>ping 60.0.0.10
Pinging 60.0.0.10 with 32 bytes of data:
Request timed out.
Request timed out.
Request timed out.
Request timed out.

Ping statistics for 60.0.0.10:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\Documents and Settings\user>ping 60.0.0.10
Pinging 60.0.0.10 with 32 bytes of data:
Reply from 60.0.0.10: bytes=32 time=1ms TTL=127
Reply from 60.0.0.10: bytes=32 time=1ms TTL=127
Reply from 60.0.0.10: bytes=32 time=2ms TTL=127
Reply from 60.0.0.10: bytes=32 time=1ms TTL=127

Ping statistics for 60.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\Documents and Settings\user>
```

```
C:\WINDOWS\system32\cmd.exe

Microsoft Windows XP [Version 5.1.2600.1
(C) Copyright 1985-2001 Microsoft Corp.

C:\Documents and Settings\user>route add 50.0.0.0 mask 255.0.0.0 60.0.0.1
C:\Documents and Settings\user>ping 50.0.0.10
Pinging 50.0.0.10 with 32 bytes of data:
Reply from 50.0.0.10: bytes=32 time=2ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127

Ping statistics for 50.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 2ms, Average = 1ms

C:\Documents and Settings\user>
```

Deleted the route

```
C:\Documents and Settings\user>route delete 60.0.0.0
C:\Documents and Settings\user>route print
=====
Interface List
0x1 ..... MS TCP Loopback interface
0x2 ..50 fe 9c 09 4f 00 ..... Intel(R) PRO/1000 MT Network Connection - Packet
Scheduler Miniport
=====
Active Routes:
Network Destination    Netmask          Gateway         Interface    Metric
50.0.0.0                255.0.0.0        50.0.0.10      50.0.0.10    10
50.0.0.10              255.255.255.255  127.0.0.1      127.0.0.1    10
50.255.255.255         255.255.255.255  50.0.0.10      50.0.0.10    10
127.0.0.0              255.0.0.0        127.0.0.1      127.0.0.1    1
224.0.0.0              240.0.0.0        50.0.0.10      50.0.0.10    10
255.255.255.255        255.255.255.255  50.0.0.10      50.0.0.10    1
=====
Persistent Routes:
None

C:\Documents and Settings\user>
```

```
C:\WINDOWS\system32\cmd.exe

C:\Documents and Settings\user>route print



Interface List
0x1 ..... MS TCP Loopback interface
0x2 ...50 86 5f 09 50 00 ..... Intel(R) PRO/1000 MI Network Connection - Packet Scheduler Miniport

Active Routes:
Network Destination    Netmask          Gateway          Interface        Metric
60.0.0.0                255.0.0.0        60.0.0.10       60.0.0.10       10
60.0.0.10               255.255.255.255  127.0.0.1       127.0.0.1       10
60.255.255.255          255.255.255.255  60.0.0.10       60.0.0.10       10
127.0.0.0               255.0.0.0        127.0.0.1       127.0.0.1       1
224.0.0.0               240.0.0.0        60.0.0.10       60.0.0.10       10
255.255.255.255        255.255.255.255  60.0.0.10       60.0.0.10       1


Persistent Routes:
None

C:\Documents and Settings\user>
```

Adding default gateway



After adding default gateway default route is appeared in route table



Ping from both the pc

