



**Select young, tender beans
free from mold and decay.
Wash beans thoroughly
and trim the ends.**

STEP

1

Pressure Canning Green Beans



Leave whole or cut beans into 1-inch pieces before packing into jars.

STEP

2

Pressure Canning Green Beans



For hot pack, cover beans with boiling water and boil for 5 minutes to blanch before packing.

! SAFETY STEP

STEP

3

Pressure Canning Green Beans



Pack hot beans loosely into hot jars, leaving 1 inch headspace.

! SAFETY STEP

STEP

4

Pressure Canning Green Beans



**Add salt if desired: 1/2
teaspoon per pint or 1
teaspoon per quart.**

STEP

5

Pressure Canning Green Beans



Cover beans with boiling water, leaving 1 inch headspace.

! SAFETY STEP

STEP

6

Pressure Canning Green Beans



Remove air bubbles by running a plastic spatula or blunt knife around the inside of the jar.

! SAFETY STEP

STEP

7

Pressure Canning Green Beans



Wipe rims of jars with a clean, damp cloth to ensure a good seal.

! SAFETY STEP

STEP

8

Pressure Canning Green Beans



Adjust lids and screw on bands fingertip tight before processing.

! SAFETY STEP

STEP

9

Pressure Canning Green Beans



Follow manufacturer's directions for venting pressure canner; vent steam steadily for 10 minutes before pressurizing.

! SAFETY STEP

STEP

10

Pressure Canning Green Beans



Process in pressure canner at 240 deg F: 10 pounds pressure with weighted gauge or 11 pounds with dial gauge at sea level.

! SAFETY STEP

STEP

11

Pressure Canning Green Beans



Process pints for 20 minutes and quarts for 25 minutes at 240 deg F under proper pressure.

! SAFETY STEP

STEP

12

Pressure Canning Green Beans



After processing, remove canner from heat and wait until pressure returns to zero before opening the lid.

! SAFETY STEP

STEP

13

Pressure Canning Green Beans



Remove lid carefully and let jars stand for 5 minutes before removing. Then cool jars on towel away from drafts for 12-24 hours.

! SAFETY STEP

STEP

14

Pressure Canning Green Beans