

Add an Activity Add an interest




- use text exactly as written
- tan background rather than white makes form elements easier to use
- title and address fields are shorter
- map is small and does not have street view or satellite view options. Also note subtle border around the map
- description field is not optional
- the photo messages, "no file chosen" and the button" add another photo" are not shown
- how do you like my inspector drawing?
- save button looks button-y. It is ghosted until required fields are entered

Add an Activity Add an interest



- on blur of a validated field, a checkmark appears.
 Checkmark is always in the upper-right hand corner, not centered. Also the background and border of fields change. On focus, they return to previous appearance.
- some interests are automatically suggested when the description field contains words that match existing interests. However, user must re-type them in to save them.
- the save button is now un-ghosted because all required fields have been entered
- if user has entered any valid fields, then if the user tries to leave the page, she gets an alert dialog, "Your activity hasn't been saved. Are you sure you want to leave this page?"



- when in the interest tags input field, upon pressing comma, tab, or enter, any text is immediately converted into a button. The tag can be removed by clicking the "x" in the button.
- once a file has been selected, the "choose file" button disappears and is replaced by the file name. Also, an "x" button appears to remove the file. Lastly, a new photo input appears (up to 3).

Add an Activity Add an interest

Enter a word or short phrase

A good description helps other members who share your interest to find it and discuss it with you.

Interests don't have a location on a map. To create something to do in a specific location, add an activity.


Do you have any cool pictures that demonstrate this interest? (optional)



Save it!

- use text exactly as written
- help text explains the difference between an interest and an activity and links to the create activity page
- tan background rather than white makes form elements easier to use
- title fields is shorter
- description field is not optional
- the photo messages, "no file chosen" and the button" add another photo" are not shown
- save button looks button-y. It is ghosted until required fields are entered





- on blur of a validated field, a checkmark appears. Checkmark is always in the upper-right hand corner, not centered. Also the background and border of fields change. On focus, they return to previous appearance.
- the save button is un-ghosted when the required fields title and description fields have been entered
- once a photo file has been selected, the "choose file" button disappears and is replaced by the file name. Also, an "x" button appears to remove the file. Lastly, a new photo input appears (up to 3).
- if user has entered any valid fields, then if the user tries to leave the page, she gets an alert dialog, "Your interest hasn't been saved. Are you sure you want to leave this page?"