

VPC Mapping Tool — Quickstart

Open the app, place structures, save — one sheet for field use.

1. Open

Open **VPC Mapping Tool.html** in Chrome, Edge, or Firefox (no install). Network needed first for imagery, search, and PDF libraries; then many features work offline.

Offline: No tiles? Enter `lat, lng` in search (e.g. `34.05, -118.25`) and **Search**.

2. First layout

1. **Site:** Header search (address or coords). **Setup** ▾ — operation name for print/PDF.
2. **Pick:** Sidebar **Vendor** tab → model. Status line shows placement mode.
3. **Place:** Click map. Repeat.
4. **Edit:** Click object — drag move; **orange handle** — rotate; delete on shape/list or **(Shift)**+click.
5. **Done:** **(Esc)** to view mode.

3. Header

- **Search** — Geocode or coords.
- **Undo / Redo** — 50 steps; lost on refresh or tab close — use **Save Plan**.
- **Measure** ▾ — Distance or area; clear when done.
- **Autosave / Restore Autosave** — Browser-only last session.

4. Sidebar

- **Label & Style** — Next label, role, color; **Snap to selected** for add-ons (select target first).
- **Options** ▾ — Opacity, rotation, **buffer** (dashed ring). Mark tight buffer as intentional in list when shown.
- **Custom Size** — **Place Custom**, then map click.
- **Plan** — **Save Plan / Open Plan; Export** ▾ GeoJSON or PDF; **Print Fit**. Enable 'Print background graphics' in your browser's print dialog for the satellite image to appear.

5. Status bar, overlaps & save

Status bar shows zoom, scale, count, and overlap summary. **Red** — footprint overlap. **Amber** — buffer advisory; adjust or mark intentional.

- **Autosave** — This browser only; not a backup.
- **Save Plan** — JSON file to archive, email, reopen anywhere.
- Fresh open by default — **Restore Autosave** for last browser session.

6. Keys

- **(/)** search · **(Esc)** view mode · **(Ctrl)+[Z]** / **(Y)** undo/redo · **(P)** place (when tent selected)

Same folder: **VPC Mapping Tool.html**. Details: **README.md**.