


1. Install Raven-Desktop-Setup.

Name	Date modified	Type	Size
 naps2-7.5.1-win	9/16/2024 9:28 PM	Application	12,010 KB
 Pro_QuickStart_Guide_v6	12/28/2023 10:15 AM	Foxit PhantomPD...	12,819 KB
 Raven_Scanner_Pro_User_Manual.docx_7	12/28/2023 10:15 AM	Foxit PhantomPD...	4,938 KB
 Raven-Desktop-Setup	12/28/2023 10:15 AM	Application	120,894 KB
 VirtualScannerLink_20211103	9/16/2024 9:25 PM	Compressed (zipp...	59,517 KB
 WTWAIN_AN360W_series_AN360W_V620...	12/28/2023 10:40 AM	Compressed (zipp...	28,328 KB

2. After installation is complete, login (If you do not have a login, I don't know if registering will work).



The image shows the Raven Desktop application window. The title bar says "Raven Desktop". The window has a light blue background with the Raven logo (a penguin) in the top left. In the center, there is a white login card. At the top of the card is the Raven logo and the text "WELCOME TO YOUR RAVEN SCANNER". Below this are two links: "SIGN IN" and "REGISTER". Under "SIGN IN", there are two input fields: "EMAIL ADDRESS" and "PASSWORD". The "PASSWORD" field has a toggle icon (an eye) to its right. Below the "PASSWORD" field is a link that says "Forgot password?". At the bottom of the card is a green button with the text "SIGN IN".

3. Choose your scanner, I am using a PRO.

1 — 2 — 3 — 4

CHOOSE YOUR SCANNER CONNECTION

Select your scanner to begin the connection process.

 **PRO**

 **PRO MAX**

 **ORIGINAL**
1ST GENERATION

 **ORIGINAL**
2ND GENERATION

 **STANDARD**

 **COMPACT**

 **GO**

CANCEL

CONTINUE


4. Select “Network connection” and press connect.

NETWORK CONNECTION


1. Ensure the scanner is plugged in and turned on.
2. Ensure your Raven Scanner is connected to the same network as your computer via Wi-Fi or Ethernet.
3. Click "CONNECT" to attempt connection to your scanner.

CONNECT

5. It will download the drivers and install them automatically, then select continue.




6. It will search for your scanner on network and connect automatically (assuming scanner is powered on and connected to network). You should hear Windows make the sound it makes when you plug in a USB device. Select OK and you should be connected.




7. Now install NAPS2.

Name	Date modified	Type	Size
 naps2-7.5.1-win	9/16/2024 9:28 PM	Application	12,010 KB
 Pro_QuickStart_Guide_v6	12/28/2023 10:15 AM	Foxit PhantomPD...	12,819 KB
 Raven_Scanner_Pro_User_Manual.docx_7	12/28/2023 10:15 AM	Foxit PhantomPD...	4,938 KB
 Raven-Desktop-Setup	12/28/2023 10:15 AM	Application	120,894 KB
 VirtualScannerLink_20211103	9/16/2024 9:25 PM	Compressed (zipp...	59,517 KB
 WTWAIN_AN360W_series_AN360W_V620...	12/28/2023 10:40 AM	Compressed (zipp...	28,328 KB

8. Open NAPS2, click arrow next to Scan, select “New Profile”, this window should pop up:



9. Name your profile (Display Name), select “Choose Device”, select “TWAIN driver”, and select the Raven scanner, then click select.



10. Adjust your scanner settings, then select OK, and you should be good to go.

