

New Virtual Machine Wizard

Specify Name and Location

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

Choose a name and location for this virtual machine.

The name is displayed in Hyper-V Manager. We recommend that you use a name that helps you easily identify this virtual machine, such as the name of the guest operating system or workload.

Name:

You can create a folder or use an existing folder to store the virtual machine. If you don't select a folder, the virtual machine is stored in the default folder configured for this server.

☒ Store the virtual machine in a different location

Location:

 If you plan to take checkpoints of this virtual machine, select a location that has enough free space. Checkpoints include virtual machine data and may require a large amount of space.

< Previous

Next >

Finish

Cancel

New Virtual Machine Wizard

Specify Generation

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

Choose the generation of this virtual machine.

☐ Generation 1

This virtual machine generation supports 32-bit and 64-bit guest operating systems and provides virtual hardware which has been available in all previous versions of Hyper-V.

☒ Generation 2

This virtual machine generation provides support for newer virtualization features, has UEFI-based firmware, and requires a supported 64-bit guest operating system.

 Once a virtual machine has been created, you cannot change its generation.

[More about virtual machine generation support](#)

< Previous

Next >

Finish

Cancel

New Virtual Machine Wizard

Assign Memory

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

Specify the amount of memory to allocate to this virtual machine. You can specify an amount from 32 MB through 251658240 MB. To improve performance, specify more than the minimum amount recommended for the operating system.

Startup memory: MB

☒ Use Dynamic Memory for this virtual machine.

i

When you decide how much memory to assign to a virtual machine, consider how you intend to use the virtual machine and the operating system that it will run.

< Previous

Next >

Finish

Cancel

New Virtual Machine Wizard

Configure Networking

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

Each new virtual machine includes a network adapter. You can configure the network adapter to use a virtual switch, or it can remain disconnected.

Connection:

< Previous

Next >

Finish

Cancel

New Virtual Machine Wizard

Connect Virtual Hard Disk

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

A virtual machine requires storage so that you can install an operating system. You can specify the storage now or configure it later by modifying the virtual machine's properties.

☒ Create a virtual hard disk

Use this option to create a VHDX dynamically expanding virtual hard disk.

Name: iip-vm-oeds-extern.vhdx

Location: F:\VirtualMachine\iip-vm-oeds-extern\Virtual Hard Disks\ Browse...

Size: 1024 GB (Maximum: 64 TB)

☐ Use an existing virtual hard disk

Use this option to attach an existing virtual hard disk, either VHD or VHDX format.

Location: F:\VirtualMachine\VirtualDisk\ Browse...

☐ Attach a virtual hard disk later

Use this option to skip this step now and attach an existing virtual hard disk later.

< Previous

Next >

Finish

Cancel

New Virtual Machine Wizard

Installation Options

Before You Begin

Specify Name and Location

Specify Generation

Assign Memory

Configure Networking

Connect Virtual Hard Disk

Installation Options

Summary

You can install an operating system now if you have access to the setup media, or you can install it later.

☒ Install an operating system later

☐ Install an operating system from a bootable CD/DVD-ROM

Media

☒ Physical CD/DVD drive:

☐ Image file (.iso): C:\ISO\ Browse...

☐ Install an operating system from a bootable floppy disk

Media

Virtual floppy disk (.vfd): Browse...


☐ Install an operating system from a network-based installation server

< Previous


Next >


Finish


Cancel





Bei CentOS-ISO kein Secure-Boot:


























iip-vm-oeds-extern on IIP-COMP103 - Virtual Machine Connection

FileActionMediaClipboardViewHelp

Done

NETWORK & HOST NAME

CENTOS STREAM 10 INSTALLATION

de

Ethernet (eth0)
The Linux Foundation Microsoft Hyper-V Network Adapter

+ -

Ethernet (eth0)
Connected

Hardware Address 00:15:5D:C6:D0:0F

Speed 1000 Mb/s

IP Address 172.23.152.114/25

Default Route 172.23.152.1

DNS 141.52.3.3
129.13.64.5

Configure...

Host Name: iip-vm-oeds-extern

Apply

Current host name: iip-vm-oeds-extern

Status: Running

iip-vm-oeds-extern on IIP-COMP103 - Virtual Machine Connection

FileActionMediaClipboardViewHelp

INSTALLATION DESTINATION

Done

CENTOS STREAM 10 INSTALLATION

de

Device Selection

Select the device(s) you'd like to install to. They will be left untouched until you click on the main menu's "Begin Installation" button.

Local Standard Disks

1024 GiB

Msft Virtual Disk 600224802e7b113cee25c21f27d0fcdf

sda / 1024 GiB free

Disks left unselected here will not be touched.

Specialized & Network Disks

Add a disk...

Disks left unselected here will not be touched.

Storage Configuration

☐ Automatic

☒ Custom

[Full disk summary and boot loader...](#)

1 disk selected; 1024 GiB capacity; 1024 GiB free [Refresh...](#)

Status: Running

iip-vm-oeds-extern on IIP-COMP103 - Virtual Machine Connection

FileActionMediaClipboardViewHelp

MANUAL PARTITIONING

CENTOS STREAM 10 INSTALLATION

de

New CentOS Stream 10 Installation

SYSTEM

/boot/efi1024 MiB

/1023 GiB

+ - ↺

AVAILABLE SPACE1.97 MiB

TOTAL SPACE1024 GiB

[1 storage device selected](#)

sda2

Mount Point:

/

Desired Capacity:

1023 GiB

Device Type:

Standard Partition

☐ Encrypt

File System:

ext4

☒ Reformat

Label:

Name:

sda2

Update Settings

Note: The settings you make on this screen will not be applied until you click on the main menu's 'Begin Installation' button.

Discard All Changes

Status: Running

