

TheWay User Manual

Version 2.7.x

Originally Created By

Comrade Doge

Current Development & Maintenance

Jonsky752

Credits

Original Project

Comrade Doge

Current Development & Maintenance

Jonsky752

Contributors

dwendelen - ABORT Button

WangNorthSea - F-15E Smart Weapon Entry, FA-18 PP MSN Entry

snakepl88 - AV8BNA Target Point Entry

Jonsky752 - SA342 Gazelle NADIR Implementation

Acknowledgements

The DCS community and all users who have contributed feedback, testing, bug reports and feature suggestions.

Introduction

TheWay is a route planning and waypoint transfer utility for DCS World.

It imports waypoints directly into supported aircraft navigation systems, providing functionality similar to a Data Transfer Cartridge (DTC).

Originally created by Comrade Doge, TheWay has since been expanded with support for additional aircraft, navigation systems and route-planning features while maintaining a simple and intuitive workflow.

Whether planning a navigation route, creating target points or preparing a complete flight plan, TheWay helps reduce cockpit workload by automating coordinate entry into supported aircraft.




Figure 1 - Waypoint created in TheWay and transferred directly into the aircraft navigation system.

Installation

1. Download the latest release ZIP file.
2. Extract the ZIP file.
3. Copy the **TheWay** folder into **Saved Games/DCS/Scripts** or **DCS.openbeta/Scripts**.
4. Add the TheWay export line to **Export.lua**:
`pcall(function() local TheWayLfs=require('lfs');dofile(TheWayLfs.writedir()..'Scripts/TheWay/TheWay.lua'); end)`
5. Run **Setup.exe** included within the downloaded release package.
6. Launch TheWay and enter the cockpit of a supported aircraft.

TheWay is designed to coexist with other export-based tools.










Figure 2 - Example Export.lua file containing multiple export-based applications.

Quick Start Guide

1. Enter the cockpit of a supported aircraft.
2. Ensure **F10 Map** is selected as the input source.
3. Open the DCS F10 Map and press the green + button.
4. TheWay's crosshair will appear.
5. Move the F10 map beneath the crosshair until the desired location is positioned under it.
6. Press **SAVE** to create the waypoint.
7. Repeat as required for additional waypoints.
8. Press **Transfer to DCS**.
9. Some aircraft may present one or more option dialogs before transfer begins.
10. Select the desired option(s) and transfer will start automatically.

Remember this choice: If selected, the chosen option will be used automatically in future and the dialog will no longer appear.

Step 1 - Connected to aircraft 	Step 3 - Press the green + button 	Step 4 - Crosshair active 
Step 6 - Waypoint saved 	Step 9 - Transfer options 	Step 10 - Transfer in progress 
Step 11 - Verify the waypoint in the aircraft		

Settings

Settings include configurable keybindings, option dialog shortcuts, crosshair options, Always On Top and Button Press Delay.

Settings

×

☒ Always on top

Keybindings

Click in the below boxes, then press a key combination. Press Delete to remove a keybinding.
Restart of the app is needed to apply the new bindings.

Toggle Crosshair

None

Save Waypoint

None

Delete Last Waypoint

None

Delete All Waypoints

None

Transfer Waypoints

None

Settings

×

Option Dialog Keybinds (op1–op4)

Option 1

None

Option 2

None

Option 3

None

Option 4

None

Crosshair options

☐ Old style crosshair

The old crosshair has customizable colors, but does not show in VR or work correctly with multiple monitors.

Button press delay

Try increasing this if buttons are pressing incorrectly, or too quickly.

+0ms+500ms

Recon Request

Recon Request may allow nearby units to be displayed and converted into waypoints for route planning and navigation.

Units returned by Recon Request can be selected individually or in groups and imported into TheWay's waypoint list. Imported units can then be edited, saved, combined with manually created waypoints, or transferred to a supported aircraft.

The availability and quantity of information returned by Recon Request may vary depending on mission design, server settings and DCS World configuration.

Coalition

Red

Type

All

Within

2

Units

nm

of

Origin

Camera position

Show table

Columns

REQUEST

IMPORT

Coalition	Type	Category	SubCategory	Capability	Position	DMM	Elev (ft)	Bearing	Range	
No units match the current filters (or no snapshot received yet).										

Press REQUEST to capture units. REQUEST again to calculate moving units. PREVIOUS SNAPSHOT MAY BE SHOWN. Check Snapshot age -->

Snapshot age: No snapshot

Coalition

Red

Type

All

Within

2

Units

nm

of

Origin

Camera position

Show table

Columns

REQUEST

IMPORT

Coalition	Type	Category	SubCategory	Capability	Position	DMM	Elev (ft)	Bearing	Range	
Red	1L13 EWR	SAM	EWB	Radar	N 41°50.520' E 41°47.881'	33	24.2'	0.0		
Red	BTR-80	Armour	APC	Gun	N 41°50.629' E 41°47.851'	33	347.7'	0.1		
Red	BTR-80	Armour	APC	Gun	N 41°50.629' E 41°47.983'	33	36.5'	0.1		
Red	BTR-80	Armour	APC	Gun	N 41°50.618' E 41°47.780'	33	217.8'	0.1		
Red	BTR-80	Armour	APC	Gun	N 41°50.319' E 41°47.921'	33	188.2'	0.1		
Red	256 Tunguska	SAM - Shorad	SA-19	Radar + Gun + M.	N 41°50.737' E 41°47.819'	33	347.9'	0.2		
Red	Tur SA331	SAM - Shorad	SA-15	Radar + Missile	N 41°50.719' E 41°48.876'	33	37.2'	0.2		
Red	Ona SA333 in	SAM - Shorad	SA-8	Radar + Missile	N 41°50.315' E 41°47.660'	33	218.1'	0.3		
Red	Kub 1058 in	SAM	SA-6	Radar	N 41°50.240' E 41°47.800'	33	188.5'	0.3		
Red	Kub 2925 in	SAM	SA-6	Missile	N 41°50.238' E 41°47.924'	32	173.8'	0.3		
Red	Kub 2925 in	SAM	SA-6	Missile	N 41°50.244' E 41°47.994'	33	183.1'	0.3		

Press REQUEST to capture units. REQUEST again to calculate moving units. PREVIOUS SNAPSHOT MAY BE SHOWN. Check Snapshot age -->


Snapshot age: 16s



NS430 Support

NS430 support is provided for aircraft that TheWay does not support through dedicated aircraft avionics. The NS430 is an add-on for DCS World. Module-specific avionics support always takes precedence over NS430 support.

For NS430 aircraft, the module image displayed by TheWay will appear in black and white.



Supported Avionics (Modules)

A-10C, A-10C II, AH-64D Apache, AV8BNA Harrier, CH-47F Chinook, C-130J-30, F-15E, F-16 family, F/A-18C/E/F/G, Ka-50, Mirage 2000, Mirage F1EE, OH-58D Kiowa Warrior, SA342 Gazelle, AH-6J/MH-6J, Hercules and UH-60L.

Supported NS430 Modules

A-10A, AJS37, Bf-109K-4, C-101CC, C-101EB, Christen Eagle II, F-14B, F-15C, F-5E-3, F-86F Sabre, FW-190D9, I-16, JF-17, J-11A, L-39C, L-39ZA, Mi-24P, Mi-8MT, MiG-15bis, MiG-21bis, MiG-29 Fulcrum, MiG-29A, MiG-29G, MiG-29S, P-51D, SpitfireLFMkIX, SpitfireLFMkIXCW, Su-25, Su-25T, Su-27, Su-33, TF-51D, UH-1H and Yak-52.