

Macarubbo, Marc Vincent G.	13/03/2026
BSIT – 601	PL

1. `print(8 + 4 % 3)`



The screenshot shows the OpenEDG Python IDE interface. The code editor contains the line `1 print(8 + 4 % 3)`. The console on the right displays the output `9`. The interface includes a 'Run' button and a Python version indicator set to 3.12.

Binding

Right-sided binding the right operator `%` is done first.

Parse Tree

```

+
/\
8 %
  /\
  4 3

```

2. `print(10 - 6 % 4)`



The screenshot shows the OpenEDG Python IDE interface. The code editor contains the line `1 print(10 - 6 % 4)`. The console on the right displays the output `8`. The interface includes a 'Run' button and a Python version indicator set to 3.12.

Binding

Right-sided binding

Parse Tree

```

-
 /\
10 %
  /\
  6 4

```

3. `print(9 % 5 + 2)`



The screenshot shows the OpenEDG Python IDE interface. The code editor contains the line `1 print(9 % 5 + 2)`. The console on the right displays the output `6`. The interface includes a 'Run' button and a Python version indicator set to 3.12.

Binding

Left-sided binding

Parse Tree

```

+
 /\
% 2
 /\
9 5

```

4. `print(7 + 2 * 3)`




The screenshot shows the OpenEDG Python IDE interface. At the top, there is a logo for OpenEDG, a 'Run' button, and icons for settings, a dark/light theme toggle, and a refresh button. The Python version is indicated as 3.12. The main editor area shows a file named 'main.py' with the code `print(7 + 2 * 3)` on line 1. The console on the right displays the output '13'.

Binding

Right-sided binding

Parse Tree



5. `print(2 ** 3 ** 2)`



The screenshot shows the OpenEDG Python IDE interface. At the top, there is a logo for OpenEDG, a 'Run' button, and icons for settings, a dark/light theme toggle, and a refresh button. The Python version is indicated as 3.12. The main editor area shows a file named 'main.py' with the code `print(2 ** 3 ** 2)` on line 1. The console on the right displays the output '512'.

Binding

Right-sided binding (exponent rule)

Parse Tree

