

Flight Options

Flight Options

Airline

https://www.airline.com

Select Flight Book Advanced Search Existing Flight Help Login

Flight Options

Departure Flights

Depart	Connection	Destination	Price/Passenger - Group
Date @ Time Location	—Duration→	Connection Date @ Time Location	—Duration→ Date @ Time Location Total Duration \$ - \$\$
Date @ Time Location	—Duration→	Connection Date @ Time Location	—Duration→ Date @ Time Location Total Duration \$ - \$\$

Departure Subtotal

Return Flights

Depart	Connection	Destination	Price/Passenger - Group
Date @ Time Location	—Duration→	Connection Date @ Time Location	—Duration→ Date @ Time Location Total Duration \$ - \$\$
Date @ Time Location	—Duration→	Connection Date @ Time Location	—Duration→ Date @ Time Location Total Duration \$ - \$\$

Return Subtotal

Subtotal Per Passenger Group

Search Select Flight Review Pay & Book!

Sort Filter

1 2 3 4 5 6 7 Continue

1. Radio Buttons - 1 button for each flight option

- On selection, radio button will fill-in and the entire horizontal block of flight information will highlight in a muted blue
- On selection, item 5, "Departure Subtotal" will update with Per Passenger and Group prices

2. Dropdown - Placeholder Text Label: "Sort"

- On selection, dropdown list will appear with options to sort "Departure Flights" by "Departure Time and Date" "Total Duration" "Number of Connections" "Destination Time and Date" and "Price"
- On selection from dropdown, dropdown will close and "Departure Flights" will reorder based on the "Sort" criteria
- After selection, text label will display the "Sort" criteria selection.
- After selection, a link using the word "Clear" will appear under the dropdown box, allowing the user to clear the sort selection

3. Dropdown - Placeholder Text Label: "Filter"

- On selection, dropdown list will appear allowing user to only view flight that meet the selected criteria: "Morning Flights" "Afternoon Flights" "Direct Flights" "Same-Day Flights" "Connection Flights"
- On selection from dropdown, dropdown will close and "Departure Flights" will only display options based on the "Filter" criteria
- After selection, text label will display the "Filter" criteria selection.
- After selection, a link using the word "Clear" will appear under the dropdown box, allowing the user to clear the filter selection

4. Progress Bar - Progress Labels: "Search" "Select Flight" "Review" "Pay & Book!"

- As the user progresses, the progress bar will fill-in to the right.
- When a user completes a step, that step-label will become a link that will take the user back to the corresponding step. In this case, "Search" is the only step that has been completed and therefore is the only active link within the progress bar.
- On selection of active link, user will navigate back to the corresponding step

5. Text Field - Label: "Departure Subtotal"

- On flight selection, fields will auto-update to display the per-passenger price in the left box and the group price in the right box

6. Text Field - Label "Subtotal"

- On flight selection, fields will auto-update to display the per-passenger price in the left box and the group price in the right box.
- This field will add both the departure and return flight subtotals

7. Button - Label: "Continue"

- On selection, user will continue to the next webpage, "Review".
- If both a Departure and Return Flight are not selected, the following error message will appear in muted red just above the button: "Please select your DEPARTURE/RETURN Flight." Departure or Return will be displayed corresponding to the missing selection

Page dimensions will vary in length depending upon the number of flight options available.

