


화면ID	KIDS-PP-US-JM-09	화면명	회원정보수정	화면 유형	입력
화면 경로	홈 > 회원정보수정 > 회원정보수정	화면 설명	회원정보수정	작업자 / 작업일시	권영주 / 2025-12-01

Header		Description	
GNB		1. 회원정보수정 입력란 영역 1.1 [Text Box - 아이디 노출 란] • 회원 아이디 노출 • 입력란 비활성화 처리 1.2. [Text Box - 이름 노출 란] • 회원의 이름 노출 • 입력란 비활성화 처리 1.3. [Text Box - 휴대전화번호 노출 란] • 회원의 휴대전화번호 노출 • 입력란 비활성화 처리 1.4. [Btn - 번호변경] • 버튼 클릭 시 Any-ID 본인인증 팝업 호출 • 본인인증이 완료된 휴대전화번호로 변경되어 노출 처리됨. 1.5. [Text Box - 이메일] • 회원의 이메일 노출 • 입력란 활성화 처리 1.6 [Btn - 중복확인] • 입력한 이메일 중복확인 처리 • 중복 이메일이 있을 경우 입력란 하단에 중복된 이메일입니다. 다른 이메일로 입력해주세요. 메시지 노출 • 중복 이메일이 없을 경우 입력란 사용 가능한 이메일입니다. 1.7 [Text Box - 비밀번호] • 비밀번호 입력란 미 클릭 시 기존 비밀번호 유지 • 비밀번호 입력란 클릭 시 새로운 비밀번호로 입력 처리함. 1.8 [Btn - 확인] • 비밀번호 입력란 클릭 시 새로운 비밀번호를 입력 받고 새로 입력받은 비밀번호와 일치하는지 유효성 검증이 적용되도록 새로운 비밀번호를 확인	
 <p>The screenshot displays the '회원정보수정' (Member Information Update) page. It features a header with a home icon and navigation links. Below the header is a title '회원정보수정'. The main content area contains several input fields with validation numbers:</p> <ul style="list-style-type: none"> 아이디 (필수): Step 1-1, value 'gdhong99'. 이름 (필수): Step 1-2, value '홍*동'. 휴대전화번호 (필수): Step 1-3, value '010-1234-5678', with a '번호 변경' button next to it. 이메일 (선택): Step 1-5, value 'gdhong99@gmail.com', with a '중복확인' button next to it. 비밀번호: Step 1-7, masked input field with a '변경' button next to it. 비밀번호 확인: Step 1-8, input field containing '비밀번호를 동일하게 입력하세요.' with a '변경' button next to it. 			
Footer			