

Barcode scanner keycode test sheet — rev 2

Device: MINJCODE MJ2818A (USB 34eb:1502) — sold as WoneNice WN3300 V3.1 · HID keyboard wedge

Print at 100% scale — do NOT "fit to page". Plain white paper, not glossy.

Method: scan in numbered order 1 → 37, pausing ~2 s between scans. If one will not read after two tries, pause and move on.

rev 2 fix: in rev 1 the two baseline barcodes were clipped by their cell and could not be read. All 37 barcodes in this revision are verified machine-decodable.

1UPC-A baseline



data: 012345678905

2Code128 baseline



data: TEST12345

30x01 · SOH



Code 128

40x02 · STX



Code 128

50x03 · ETX



Code 128

60x04 · EOT



Code 128

70x05 · ENQ



Code 128

80x06 · ACK



Code 128

90x07 · BEL



Code 128

100x08 · BS



Code 128

△ natural key: Backspace

110x09 · HT



Code 128

△ natural key: Tab

120x0A · LF



Code 128

△ natural key: Enter

130x0B · VT



Code 128

140x0C · FF



Code 128

150x0D · CR



Code 128

△ natural key: Enter

160x0E · SO



Code 128

170x0F · SI



Code 128

180x10 · DLE



Code 128

190x11 · DC1



Code 128

200x12 · DC2



Code 128

210x13 · DC3



Code 128

220x14 · DC4



Code 128

230x15 · NAK



Code 128

240x16 · SYN



Code 128

25

0x17 · ETB



Code 128

26

0x18 · CAN



Code 128

27

0x19 · EM



Code 128

28

0x1A · SUB



Code 128

29

0x1B · ESC



Code 128

⚠ natural key: Escape

30

0x1C · FS



Code 128

31

0x1D · GS



Code 128

32

0x1E · RS



Code 128

33

0x1F · US



Code 128

34

0x01 · SOH



Ext. Code 39

35

0x02 · STX



Ext. Code 39

36

0x03 · ETX



Ext. Code 39

37

0x1B · ESC



Ext. Code 39

⚠ natural key: Escape