

FINAL RTR-01 Config

Below is the final configuration output of the Edge Router, RTR-01:

```
RTR-01#show run
Building configuration...
Current configuration : 1734 bytes
!
version 15.1
no service timestamps log datetime msec
no service timestamps debug datetime msec
service password-encryption
!
hostname RTR-01
!
!
no ip cef
no ipv6 cef
!
!
username admin privilege 15 secret 5 $1$mERr$vTbHul1N28cEp8lkLqr0f/
!
!
license udi pid CISCO2811/K9 sn FTX1017V124-
!
!
ip ssh version 2
ip ssh time-out 60
!
!
spanning-tree mode pvst
!
!
interface FastEthernet0/0
description ISP-Facing
```

```
no ip address
ip access-group ACL_WAN_IN in
ip nat outside
duplex auto
speed auto
!
interface FastEthernet0/1
description Inside-Facing
ip address 203.0.113.2 255.255.255.252
ip nat inside
duplex auto
speed auto
!
interface Vlan1
no ip address
shutdown
!
ip nat inside source static 10.50.40.10 203.0.113.20
ip classless
ip route 10.50.10.0 255.255.255.0 203.0.113.1
ip route 10.50.20.0 255.255.255.0 203.0.113.1
ip route 10.50.30.0 255.255.255.0 203.0.113.1
ip route 10.50.40.0 255.255.255.192 203.0.113.1
ip route 10.50.50.0 255.255.255.192 203.0.113.1
ip route 203.0.113.10 255.255.255.255 203.0.113.1
ip route 203.0.113.20 255.255.255.255 203.0.113.1
!
ip flow-export version 9
!
!
ip access-list standard NAT_TRAFFIC
permit 10.50.10.0 0.0.0.255
permit 10.50.20.0 0.0.0.255
permit 10.50.30.0 0.0.0.255
permit 10.50.40.0 0.0.0.63
permit 10.50.50.0 0.0.0.63
ip access-list extended ACL_WAN_IN
permit tcp any host 203.0.113.20 eq 443
```

```
permit icmp any any echo-reply
permit udp any any eq 443
!
banner motd ^C
AUTHORIZED ACCESS ONLY. All activity is monitored and logged.
Unauthorized access is prohibited and will be prosecuted.
^C
!
!
line con 0
login local
!
line aux 0
!
line vty 0 4
login local
transport input ssh
line vty 5 15
login local
transport input ssh
!
!
!
end
RTR-01#
```