



Enterprise Asset Management (EAMS) v15

Work Request and Portal

End User Documentation

Update 3/1/2024


Work Request

The MaintStar Service Request Module is a licensed resource and is a versatile, and user configurable web-based application that allows service requests to be created and submitted. Once submitted they can be held for review, and approved requests can be turned into actual work orders in the MaintStar system without having to be re-entered. Work Requests can be entered or submitted via a MaintStar Portal, the Mobile Citizen application, or by staff (usually as a result of phone calls/emails). The system has been designed to serve 3 different audiences of users:

- **Internal Users** - An Internal user would be an individual who works in house for the organization. This individual can use the system as a quick and easy way to create work requests. The Internal User might be a maintenance staff person, a maintenance clerk, or a non-maintenance person employed by the organization to request services from the maintenance department.
- **External User** - An External User would be an individual from outside the organization who needs to submit a request for services. In the case of a municipality, an external user would be a citizen from the community. The system will allow an external user to create a user profile and log in, or request services anonymously.
- **Administrative User** - an administrative user would be an authorized individual who sets up the configuration of the module, controls customization of screens, and the rights of the internal and external users. The administrative user can also view and control and create reports about the actual requests generated in the system.

The Work Request screen is located under the Work Request menu. Work Request menu items consist of:

- Work Request: Similar to the Work Order screen, this lists all Work Requests submitted/created.
NOTE: these are not yet assigned Work Orders, these are just requests
- WR Settings: contains all the settings for Work Requests, Portal, Notifications, etc
- Customers: a listing of all registered customers (submitters)
- WR Reports: predefined WR reports



Viewing Work Requests

Work Requests can be viewed from under the Work Request, Work Request menu. The look of feel of Work Requests is very similar to Work Orders. Work Requests can be viewed in either the Grid or Card views by activating the icon in the lower right corner of the screen.

The screenshot displays the MAINTSTAR Asset Management interface. On the left is a sidebar menu with options like Home (admin), Work Order, Work Request, and various settings. The main area is divided into two panels. The left panel shows a list of work requests with columns for ID, status, location, and date. The right panel shows the detailed view for Work Request WR24001451, which is currently 'In Process'. This panel includes tabs for Details, Assets, Attachments, Related, Status, and Duplicates. The 'Details' tab is active, showing fields for Request and Work Order status, Request Information, and Contact Information.

Request and Work Order status	
WReq #	WR24001451
Issued WO #	F000026467
WR Status	In Process
WO Status	Open
Created	03/04/2024 10:39 AM
WO Created	03/04/2024 10:39 AM
Closed	
WO Closed	
WR Target	03/04/2024
WO Target	03/04/2024
Assigned To	
Priority	
WO Workgroup	FACIL
Origin Code	Desktop
Primary Request	
Crew leader	
Refer Division	
Supervisor	

Contact Information	
Customer Type	
Customer ID	
Customer Name	
Primary Phone	+1
Phone 2	+1

Common Work Request tabs:

- **Details:** is the main request screen
- **Assets:** can be used to add assets to the request before it is made into a work order. Note, you can also have an asset field on the main request screen if you want your requester to select an asset.
- **Related:** can be used to associate other requests that are like this one.
- **Attachments:** is where uploaded pictures will be stored
- **Create WO:** turns the request into a work order
- **Duplicate:** Shows you other requests from the same location

WR Settings

The Work Request setting section is used to configure your requests. The section has 6 tabs:

- **WR Control:** sets default WR parameters
- **Operations:** defines the operations, ie "Pothole" or "Facilities Request"
- **Groups:** multiple groups can be created to support multiple portals
- **Portal Settings:** controls the portal

WR Control Sceren

This screen sets many of the default behaviors for Work Requests. This is typically an admin only function.

- **WR Pattern:** sets the work request ID patter can be set as shown Examples: WR0 -> WR00000001, WR# -> WR1, WR{YY}0 -> WR20000001.
- **Last WR Number:** controls the starting number. This is helpful if you are coming from another system and want to carry numbers forward.
- **WR Desktop Settings:** has default settings for State, city, and promised date.
- **Default Group:** important if you are allowing users to self-register. This determines which user group they will be defaulted to.
- **Allow Anonymous:** controls whether the portal will allow users to submit requests without registering for an account.

Operations Tab

The Operations tab holds 3 levels of choices for your requestors to choose from. You must use the operation level. These levels of choices make it easy for your audience to categorize their issue so that you get reliable actionable information. These categories also allow reporting by category. The Operation level is typically configured to be a list of “Departments” or Operations” in your agency.

Examples would be: Facilities, Fleet, Water, Streets and Roads, etc. In a manufacturing environment, operations might be different manufacturing areas in your plant. The response they give to the first tier, or complaint question will determine which set of questions they see in the second tier or problem.

Example: If your organization was a facility maintenance group you might create the first tier of questions (complaint) something like this:

First Tier “Operations”

The requestor chooses Facilities at the operation level

- Facilities
- Graffiti
- Streets
- Water

Second tier of “Issues”

The requestor selects plumbing from the facilities options at the second level.

- HVAC
- Plumbing
- Electrical
- Room furnishing

If the requestor chose Plumbing, the Third Tier of “Issue details” might be:

- Leaking Sink
- Clogged Sink
- No Hot Water
- Toilet Clogged

When they make these selections, their responses are stored in the request and will transfer to the work order. They can still add an additional comment into the complaint box if they want to.

Click add to add a new operation. Click edit to edit an existing line.

	Op Name	Op Description	Notify Users	WorkGroup	Printout	Customize	Added By	Added Date	Updated By	Updated Date	Op Id
☐ Edit	PublicWorks	Public Works	ACASTILLO	FACIL	144	Customize	VICTOR	06/26/2019	BSMITH	11/05/2020	1
☐ Edit	Transportation	Transportation	BRETT, BPRATER	TRANSP	144	Customize	VICTOR	11/14/2019	Maria	08/26/2020	2
☐ Edit	Fleet	Fleet Department	BGABBANI	FLEET	149	Customize	ERIC	02/21/2020	Maria	08/03/2020	3
☐ Edit	Water	Water	kadrick, bob	WATER	144	Customize	ERIC	02/24/2020	VICTOR	08/27/2020	4
☐ Edit	Storm	Storm Water	BKIDD	STORM	144	Customize	BRETT	06/08/2020	Admin	10/27/2020	5
☐ Edit	Facility	Facility	dbm, BPRATER	FACIL	144	Customize	BRETT	06/19/2020	Maria	08/26/2020	6
☐ Edit	test				144	Customize	Maria	08/26/2020	Admin	10/27/2020	7

- Notify users -Select one or more names from your user dropdown for staff who should be notified when a request for this operation level comes in.
- Workgroup Select the workgroup that should get a work order made for this operation code.
- Printout Select a printout form for the requests that come from this operation.
- Allow public Requests This checkbox controls if this operation is shown on the portal.
- Customize links you to the screen to make customizations for this operation code on the screen.

The second level called Issue (was called complaint in version 14) is developed by clicking on the operation first. Each operation level code has its own secondary issue list.

The issues are developed in the same way as the operation level.

Issues										
ADD SAVE RESET										
☐ Edit	Issue Name	Issue Description	Notify Users	Priority	Promised Days	Added By	Added Date	Updated By	Updated Date	Issue Id
☐ Cancel	Pothole	Pothole in street	BRETT x ADELEON x	2 - Medium	10	BRETT	06/08/2020	Maria	08/04/2020	16
☐ Edit	Wire Down	Wire in Street	BKIDD, BRETT	OM	5	BRETT	06/08/2020	Maria	08/26/2020	17
☐ Edit	Need Repaving	Repave street		3	20	BRETT	06/08/2020	Maria	08/25/2020	18

The third level is issue detail. This level gives you more granularity to your responses. This level does not have the option to route to internal staff with email notifications. It is built the same way as the issue is built. Click on an issue to add issue detail as a third level.

MAINTSTAR

Full Menu:

Home (BSMITH)

Work Order

Work Request

Work Request

WR Settings

Customers

WR Reports

WR Mass Deletion

Asset

Asset Management

Inventory

Reporting

Work Planning

Purchase Orders

FACIL

Edit

Fleet

Fleet Department

GBAGBANI

FLEET

149

Customize

ERIC

02/21/2020

Maria

08/03/2020

Edit

Water

Water

kadrick bob

WATER

144

Customize

ERIC

02/24/2020

VICTOR

08/27/2020

Edit

Storm

Storm Water

BKIDD

STORM

144

Customize

BRETT

06/08/2020

Admin

10/27/2020

Edit

Facility

Facility

dbm, BPRATER

FACIL

144

Customize

BRETT

06/19/2020

Maria

08/26/2020

Edit

test

144

Customize

Maria

08/26/2020

Admin

10/27/2020

Issues

ADD

Edit

Issue Name

Issue Description

Notify Users

Duplicate Mode

Priority

Promised Days

Added By

Added Date

Updated By

Updated Date

Issue Id

Edit

Electrical Issues

lights out

David

06/26/2020

David

06/26/2020

21

Edit

plumbing issues

David

06/26/2020

22

Edit

HVAC issue

David

06/26/2020

23

Edit

Graffiti

Long

08/26/2020

31

Issue Details

ADD

Edit

Concern Name

Concern Description

Added By

Added Date

Updated By

Updated Date

Id

Edit

no power

David

06/26/2020

14

Edit

brown out

David

06/26/2020

15

Edit

other

David

06/26/2020


16

Groups

The groups tab allows you to create groups of users. Click new group to create a group. Each group can be controlled for:


- Which users belong in each group
- Which operation codes each group should see
- What notifications each group should get.

For a municipality, you will have several groups. Let's say you have one for general staff. These requestors could ask for services for all operation level choices, so you add all operation codes to this group. You also are opening the system to the general public. You would want operations for road issues, graffiti and other municipal services activated but you would not want facilities or fleet available to the public only internal staff.




Operations

The operations tab lists the operations this group will see, Add button adds additional operation to the group. The check mark on the left will select an operation to delete.



Notifications

The Email Notifications are configured here. The blue checkbox activates the email notice. You must have a template specified for each notification event. The blue box on the right of each template will jump you to the template setup screen.



Portal Settings Tab

The Portal is a Simplified set of screens intended for users to use to submit requests. Users can access the portal without having access to the rest of MaintStar. Most agencies will have one portal for their requesters to use. It is however possible to have more than one portal configured for different users. You may want a portal configured for a DMZ for an additional layer of security.

The table at the top of the screen is a list of your available portals. These are not user configurable.

WR SETTINGS

WR Control Operations Groups **Portal Settings** Status Customer Type

Full Menu:
Home (BSMITH)
Work Order
Work Request
Work Request
WR Settings
Customers
WR Reports
WR Mass Deletion

Asset
Asset Management
Inventory
Reporting
Work Planning
Purchase Orders
Invoicing
Fleet
Setup
Security

ADD 1 / 1 by 10

Portal Id	Portal Description	Server Url
2	internal	https://dev2.maintstar.co/portal/#/p-2
4		https://dev2.maintstar.co/portal/#/p-4
5		https://dev2.maintstar.co/portal/#/p-5
6	TESTING--- NEW	https://dev2.maintstar.co/portal/#/p-6
10	External	https://dev2.maintstar.co/portal/#/p-10
17		https://dev2.maintstar.co/portal/#/p-17

Portal #2

URL: https://dev2.maintstar.co/portal/#/p-2

Portal Description: internal

Default Group: General Public

Default State: CA

Default City: Irvine

Agency Contact Phone:

☒ Allow Anonymous Requests
☒ Allow Registration
☐ Accept request from Mobile Citizen
☒ Automatic linkage of duplicate requests

☐ Captcha enabled
☐ Send survey in email
☒ Enable Google Map

Show dup. within 1000 feet Show dup. within 10 days

Validate Street Name:

SAVE

FACIL

Please contact MaintStar support for assistance if you wish to add additional portals to your system.

Status Tab

Status values can be set to automatically update Work Requests (and send notifications) to submitters. The system has 4 internal system statuses, although more can be configured.

- New -New request, no action taken
- In work – Work Order has been made from this request
- Done (closed) – Work request is closed either manually or automatically from work order being closed)
- Denied (closed)- Work Request closed from the request being denied.

WR Control Operations Groups Portal Settings Status Customer Type							
ADD 1 / 1 by 30							
	Seq No	Status	Description	System Status	Default	Color	Mobile Citizen Status ID
☐ Edit		In Work	In Work		☐		In Progress
☐ Edit		In Review	Needs Approval		☐		Submitted
☐ Edit		Rejected	Rejected		☐		Denied
☐ Edit	1	New		New	☒	Blue	New
☐ Edit	2	Draft		New	☐	Blue	Submitted
☐ Edit	3	Reviewing		New	☐	Blue	
☐ Edit	4	Approved		New	☐	Yellow	New
☐ Edit	5	In Process		In Work	☒	Green	In Progress
☐ Edit	6	Denied		Denied (Closed)	☒	Red	Denied
☐ Edit	7	Done		Done (Closed)	☒	Gray	Closed

Customer Type

The customer type allows you to create categories for customers. Customer type is a field on the request screen used to categorize different types of requesters such as telephone, email, walk-in or portal, etc.

Code	Description
email	email
Telephone	Telephone
Other	Other customer not listed
Other city/county	Other city/county
Public Citizen	Public Citizen
SHERIFF/CHP/POLICE/FIRE	SHERIFF/CHP/POLICE/FIRE

Customers

The Customers table holds all requesters. People who self-register to use the system are stored here. MaintStar users who log into the request portal from their MaintStar ID are copied over to this table, and users you create manually are created here. The filter section at the top of the screen is the list of all customers. It can be filtered as we do work orders and other tables in the system.

Customer ID	Name	Address	City	State	Zip	Phone	Fax	Active	Add By	Add Dt	Upd By	Upd Dt
CHRIS	CINDY	3561 BALLANTYNE DR	PLEASANTON	CA				☒	Convert	06/14/2019		
DEBBIE	DEBBIE	6302 CALLE ALTAMIRA	PLEASANTON	CA				☒	Convert	06/14/2019		
FRED	FRED	219 DIVISION	PLEASANTON	CA				☒	Convert	06/14/2019		
HUDSON, BOB	HUDSON, BOB	3789 SARATOGA	PLEASANTON	CA				☒	Convert	06/14/2019		
JOSE	JOSE	FIRST & BERNAL	PLEASANTON	CA				☒	Convert	06/14/2019		
KAREN	KAREN	4184 DENKER DR	PLEASANTON	CA				☒	Convert	06/14/2019		
KELLY	KELLY	472 ST JOHN STREET	PLEASANTON	CA				☒	Convert	06/14/2019		
MARY	MARY	SILVER STREET	PLEASANTON	CA				☒	Convert	06/14/2019		
MIKE	MIKE	OWENS DR	PLEASANTON	CA				☒	Convert	06/14/2019		

A selected user (blue highlight) is displayed in detail at the bottom of the screen.


The screenshot displays the MAINTSTAR interface for editing a customer profile. At the top, a table lists users: MARY and MIKE, with columns for conversion status and dates. The main content area is titled 'Customer: HUDSON, BOB' and includes tabs for Details, Work Orders, Work Requests, Borrowing, and Attachments. The 'Details' tab is active, showing fields for Customer ID (HUDSON, BOB), Customer Name (HUDSON, BOB), User Name, Account, Contact (CITY PERSONNEL), Address Key, Street No, Street Name, City (PLEASANTON), State (CA), Zip, Cross Street, Address 1 (FIRST & BERNAL), Address 2, Cell Phone (9259315650), and Phone 2. There are also fields for Billing Address (Bill Name, Bill Address, City, State, ZIP), Discount Percentage (Labor, Parts, Misc., Payment), and Payment Term (Parts Tax, Misc. Tax, Prompt, Net). On the right, there are checkboxes for 'Notify Via Email', 'By Text Message', 'Bill Flag', 'Internal User', 'Banned', and 'Banned Until'. There are also fields for 'Ban Reason', 'Account Expire', 'Last PW Change', 'Company', and 'Department'. A sidebar on the left contains navigation links: Home (VICTOR), Work Order, Work Request, Work Request Settings, Customers, WR Reports, WR Mass Deletion, Asset, Asset Management, Inventory, Reporting, Work Planning, Purchase Orders, Invoicing, Fleet, Setup, and Security. At the bottom left, there is a 'FACIL' dropdown menu.

The customer table is used in many sections of the system for many different things. In the request the Key parts of the record are:

- **Customer ID** - Unique identifier. This is used when the person logs in to the request
- **Customer Name** - First and last name
- **Username** – MaintStar user name (filled in for MaintStar users who sign into the request portal)
- **Phone**
- **Email**
- **Notify via email** – send notices to MaintStar notifications.
- **By external email** – send notices to email address in profile.
- **Notify by text** – send notices by SMS text message to phone in cell phone in profile.
- **Internal user** – denotes this person is a MaintStar system user.
- **Banned** – used to block a user from submitting requests.
- **Work Request** tab lists Requests this user has submitted.

Portal

The portal is a public or private facing resource from which submitters can enter Work Requests to the organization. It is a simpler web interface designed for your requestors to use to submit their requests. The Portal has its own URL address. Most agencies will have one portal, but it is possible to set up more than one. The portal can be viewed on a tablet, phone or desktop screen. The screen will automatically adjust the screen based on the device.



Request list – Shows list of either my requests or all requests by tab selection. Blue Id link will open the detail of each request. Requests are color coded for status. The Small funnel at the top of the list opens a filter to show open, closed or both status. It also lets you filter for a operation type.

Start a new request with the “Add a new request button”.

Map Will show location of requests that were geo tagged. If your phone or tablet has location services activated your location will be stored on the map when you submit requests. Those requests with this map information are notated with the black pinpoint icon in the first column of the list.

Map Icon will display or close the map.

Tab to show

- my requests (ones you have made)
- Tagged requests (Ones you have checked tag box, to keep your eye on)
- All Requests – show all requests from all users (May be security controlled for different user groups to show or not show)

Menu to change your user information, add a new request or logout

Entry screen

First select an Operation code and then an issue. Depending on configuration there may be a third level "Issue details: These will be checkboxes. Red Star denotes a required field


The screenshot shows the 'Add new request' screen. At the top, there is a blue navigation bar with links for 'My Req', 'My Tagged Req', and 'All Req'. Below the navigation bar, the title 'Add new request' is centered. The main content area has a light gray background. It contains two dropdown menus: 'Select an Operation' with 'Transportation' selected, and 'Select an Issue' with 'Pothole' selected. Below these, there is a section for 'Select Issue Details' with two checkboxes: 'one big pothole' (checked) and 'Many Small potholes' (unchecked). A red speech bubble with the text 'Click NEXT to move to next screen' points to a blue 'Next' button at the bottom right of the form.

The next screen is the primary request screen. It will vary according to the screen customization. It states your identity, location and text description of the issue. At the bottom of the screen you can attach photos or files to the request. These will transfer to the work order. If you are using a phone or camera you can take pictures and attach them to the request.

The final step is to submit the request.

The screenshot shows the primary request screen. It has a blue navigation bar at the top with links for 'My Req', 'My Tagged Req', and 'All Req'. The main content area is a form with various fields: 'Street Name' (Meade Hollow), 'Cross Street', 'City' (Orwell), 'State' (OH), 'ZIP' (44076), 'Location Description' (Right from Noble road), 'Request', 'Email', 'Phone', and 'Asset'. A white modal box is centered on the screen with the title 'Thank you!' and the text 'You submitted an issue #WR20000153. If this an emergency, call 911.' Below the text are two buttons: 'Open My Requests' and 'Open All Requests'. A red speech bubble with the text 'Confirmation of Submission' points to the modal box. At the bottom of the form, there are 'Return' and 'Submit' buttons.

The request is now submitted for processing.



The Request will now appear in the Request section of the MaintStar application.