

Accès wifi quai de livraison

Configuration Borne Wifi

```
hostname ap
!
enable secret 5 $1$uJ6z$wspHa0ob5YvRAn35mvHjy.
!
ip subnet-zero
ip domain name stadiumcompany.local
!
!
aaa new-model
!
!
aaa group server radius rad_eap
!
aaa group server radius rad_mac
!
aaa group server radius rad_acct
!
aaa group server radius rad_admin
cache expiry 1
cache authorization profile admin_cache
cache authentication profile admin_cache
!
aaa group server tacacs+ tac_admin
cache expiry 1
cache authorization profile admin_cache
cache authentication profile admin_cache
!
aaa group server radius rad_pmip
!
aaa group server radius dummy
!
aaa authentication login eap_methods group rad_eap
aaa authentication login mac_methods local
aaa authorization exec default local
aaa accounting network acct_methods start-stop group rad_acct
aaa cache profile admin_cache
all
!
aaa session-id common
!
dot11 ssid Logistic Access
    authentication open eap eap_methods
    authentication network-eap eap_methods
```

```
    guest-mode
!
power inline negotiation prestandard source
!
!
username Cisco password 7 1531021F0725
!
bridge irb
!
!
interface Dot11Radio0
no ip address
no ip route-cache
!
ssid Logistic Access
!
speed basic-1.0 basic-2.0 basic-5.5 6.0 9.0 basic-11.0 12.0 18.0 24.0 36.0 48.0 54.0
station-role root
bridge-group 1
bridge-group 1 subscriber-loop-control
bridge-group 1 block-unknown-source
no bridge-group 1 source-learning
no bridge-group 1 unicast-flooding
bridge-group 1 spanning-disabled
!
interface Dot11Radio1
no ip address
no ip route-cache
shutdown
!
ssid Logistic Access
!
speed basic-6.0 9.0 basic-12.0 18.0 basic-24.0 36.0 48.0 54.0
station-role root
bridge-group 1
bridge-group 1 subscriber-loop-control
bridge-group 1 block-unknown-source
no bridge-group 1 source-learning
no bridge-group 1 unicast-flooding
bridge-group 1 spanning-disabled
!
interface FastEthernet0
no ip address
no ip route-cache
duplex auto
speed auto
bridge-group 1
no bridge-group 1 source-learning
```

```
bridge-group 1 spanning-disabled
!
interface BVI1
ip address 172.20.5.2 255.255.255.0
no ip route-cache
!
ip default-gateway 172.20.1.1
ip http server
no ip http secure-server
ip http help-path http://www.cisco.com/warp/public/779/smbiz/prodconfig/help/eag
ip radius source-interface BVI1
!
snmp-server view dot11view ieee802dot11 included
snmp-server community public view dot11view RO
radius-server attribute 32 include-in-access-req format %h
radius-server vsa send accounting
!
control-plane
!
bridge 1 route ip
!
!
!
line con 0
transport preferred all
transport output all
line vty 0 4
transport preferred all
transport input all
transport output all
line vty 5 15
transport preferred all
transport input all
transport output all
!
end
```

Mise en place ACL

```
ip access-list extended ACL_VLAN50_OUT
deny ip 192.168.50.0 0.0.0.255 192.168.10.0 0.0.0.255
deny ip 192.168.50.0 0.0.0.255 192.168.20.0 0.0.0.255
deny ip 192.168.50.0 0.0.0.255 192.168.30.0 0.0.0.255
permit ip any any
```

```
ip access-list extended ACL_VLAN50_IN
deny ip 192.168.10.0 0.0.0.255 192.168.50.0 0.0.0.255
deny ip 192.168.20.0 0.0.0.255 192.168.50.0 0.0.0.255
deny ip 192.168.30.0 0.0.0.255 192.168.50.0 0.0.0.255
permit ip any any
```

```
interface GigabitEthernet0/0/0.50
encapsulation dot1Q 50
ip address 192.168.5.1 255.255.255.0
ip access-group ACL_VLAN50_IN in
ip access-group ACL_VLAN50_OUT out
```