


AWS EC2

Launch instance



Launch an instance [Info](#)

Amazon EC2 allows you to create virtual machines, or instances, that run on the AWS Cloud. Quickly get started by following the simple steps below.

Name and tags [Info](#)

Name

django-web

[Add additional tags](#)

▼ Application and OS Images (Amazon Machine Image) [Info](#)


An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

🔍 Search our full catalog including 1000s of application and OS images

Recents

My AMIs

Quick Start



🔍
[Browse more AMIs](#)
Including AMIs from
AWS, Marketplace and
the Community

Amazon Machine Image (AMI)

Amazon Linux 2023 kernel-6.18 AMI
ami-08c64967154312fa5 (64-bit (x86), uefi-preferred) / ami-042b179429a214d2d (64-bit (Arm), uefi)
Virtualization: hvm ENA enabled: true Root device type: ebs

▼ Summary

Number of instances [Info](#)

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.12.....[read more](#)
ami-08c64967154312fa5

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

📘 **Free tier:** In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as

[Cancel](#)

[Launch instance](#)

[Preview code](#)

Amazon Machine Image (AMI)

Amazon Linux 2023 kernel-6.18 AMI
ami-08c64967154312fa5 (64-bit (x86), uefi-preferred) / ami-042b179429a214d2d (64-bit (Arm), uefi)
Virtualization: hvm ENA enabled: true Root device type: ebs

Description

Amazon Linux 2023 (kernel-6.18) is a modern, general purpose Linux-based OS that will be supported until June 2029. It is optimized for AWS and designed to provide a secure, stable and high-performance execution environment to develop and run your cloud applications.

Amazon Linux 2023 AMI 2023.12.20260710.0 x86_64 HVM kernel-6.18

Architecture

64-bit (x86)

Boot mode

uefi-preferred

AMI ID

ami-08c64967154312fa5

Publish Date

2026-07-10

Username

ec2-user

Verified provider

▼ Instance type

Info | Get advice

Instance type

t3.micro

Family: t3 2 vCPU 1 GiB Memory Current generation: true On-Demand Windows base pricing: 0.0222 USD per Hour
On-Demand Linux base pricing: 0.013 USD per Hour On-Demand RHEL base pricing: 0.0418 USD per Hour
On-Demand SUSE base pricing: 0.013 USD per Hour On-Demand Ubuntu Pro base pricing: 0.0165 USD per Hour

Free tier eligible

All generations

Compare instance types

Additional costs apply for AMIs with pre-installed software

▼ Key pair (login)

Info

▼ Summary

Number of instances Info

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.12.....read more
ami-08c64967154312fa5

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Free tier:

In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as

Cancel

Launch instance

Preview code

▼ Key pair (login) [Info](#)

You can use a key pair to securely connect to your instance. Ensure that you have access to the selected key pair before you launch the instance.

Key pair name - *required*

django-keypair

↻ Create new key pair

▼ Network settings [Info](#)

Network [Info](#)

vpc-0e092393ffbd671b9

Subnet [Info](#)

No preference (Default subnet in any availability zone)

Auto-assign public IP [Info](#)

Enable

Additional charges apply when outside of free tier allowance

Firewall (security groups) [Info](#)

A security group is a set of firewall rules that control the traffic for your instance. Add rules to allow specific traffic to reach your instance.

☐ Create security group

☒ Select existing security group

Common security groups [Info](#)

Select security groups

↻ Compare security group rules

default sg-0b8eb5ef628718991 ✕
VPC: vpc-0e092393ffbd671b9

Security groups that you add or remove here will be added to or removed from all your network interfaces.

▼ Summary

Number of instances [Info](#)

1

Software Image (AMI)

Amazon Linux 2023 AMI 2023.12....[read more](#)
ami-08c64967154312fa5

Virtual server type (instance type)

t3.micro

Firewall (security group)

default

Storage (volumes)

1 volume(s) - 8 GiB

❗ **Free tier:** In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as

Cancel

Launch instance

🔗 Preview code

▼ Configure storage [Info](#)

Advanced

1x 8 GiB gp3 ▼ Root volume, 3000 IOPS, Not encrypted

① Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage

Add new volume

🕒 Click refresh to view backup information

The tags that you assign determine whether the instance will be backed up by any Data Lifecycle Manager policies.

🔄

File systems

☐ S3 Files - new

☐ EFS

☐ FSx

☒ None

▶ Advanced details [Info](#)

Software Image (AMI)
Amazon Linux 2023 AMI 2023.12.....[read more](#)
ami-08c64967154312fa5

Virtual server type (instance type)
t3.micro

Firewall (security group)
default

Storage (volumes)
1 volume(s) - 8 GiB

① Free tier: In your first year of opening an AWS account, you get 750 hours per month of t2.micro instance usage (or t3.micro where t2.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GB of snapshots, and 100 GB of bandwidth to the internet. Data transfer charges are not included as

Cancel

➡ Launch instance

[Preview code](#)

생성 중...

The screenshot shows the AWS Management Console interface for the 'Instances' page. The left sidebar contains navigation links for EC2, Dashboard, AWS Global View, Events, and Instances. The main content area displays a table of instances. The instance 'django-web' with ID 'i-055797a41d1ce1a78' is shown in the 'Running' state. The 'Status check' column for this instance shows '1 Initializing', which is highlighted with a red box. The table headers include Name, Instance ID, Instance state, Instance type, Status check, Availability Zone, Public IPv4 DNS, and Public IPv4

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IPv4 ...
django-web	i-055797a41d1ce1a78	Running	t3.micro	1 Initializing	ap-northeast-2c	ec2-43-201-18-6.ap-no...	43.201.18.6

생성 완료

The screenshot shows the AWS Management Console interface for the 'Instances' page. The instance 'django-web' with ID 'i-055797a41d1ce1a78' is shown in the 'Running' state. The 'Status check' column for this instance now shows '3/3 checks passed', indicating that the instance is fully operational. The table headers include Name, Instance ID, Instance state, Instance type, Status check, Availability Zone, Public IPv4 DNS, Public IPv4 ..., and Elastic IP.

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IPv4 ...	Elastic IP
django-web	i-055797a41d1ce1a78	Running	t3.micro	3/3 checks passed	ap-northeast-2c	ec2-43-201-18-6.ap-no...	43.201.18.6	-

Security Groups

Security Groups (1/1) Info

Find security groups by attribute or tag

☒	Name	Security group ID	Security group name	VPC ID	Description
☒	-	sg-0b8eb5ef628718991	default	vpc-0e092393ffbd671b9	default VPC security group

sg-0b8eb5ef628718991 - default

Details **Inbound rules** Outbound rules Sharing VPC associations Related resources - new Tags

Inbound rules (3)

Search

☐	Name	Security group rule ID	IP version	Type	Protocol	Port range
☐	-	sgr-067b596de78f5b495	IPv4	SSH	TCP	22
☐	-	sgr-0f8d5f1a90c259a25	IPv4	HTTP	TCP	80
☐	-	sgr-0dc3c36990aa6c4ba	-	All traffic	All	All

도커 설치 on EC2

The screenshot shows the AWS Management Console interface for the EC2 service. The left sidebar contains navigation links for EC2, Dashboard, AWS Global View, Events, and Instances. The main content area displays the 'Instances (1/1)' page. A table lists the instance 'django-web' with ID 'i-055797a41d1ce1a78', state 'Running', type 't3.micro', and status '3/3 checks passed'. A red box highlights the instance name 'django-web'. A red arrow points to the 'Connect' button in the top right corner of the instance details section.

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IPv4
django-web	i-055797a41d1ce1a78	Running	t3.micro	3/3 checks passed	ap-northeast-2c	ec2-43-201-18-6.ap-no...	43.201.18.6

In web browser

In SSH client

Choose how to connect

☒ Public subnet access

Managed SSH keys

EC2 Instance Connect
Use for instances with public IPs or accessible via standard routing. Requires network connectivity to your instance. Connect using temporary SSH keys managed by AWS.

☐ Private subnet access

Managed SSH keys

EC2 Instance Connect Endpoint
Use for instances in private subnets. Traffic is routed through a VPC endpoint. Connect using temporary SSH keys managed by AWS.

☐ Maximum security

IAM authentication

SSM Session Manager
Uses IAM-based authentication. Connect without SSH keys, bastion hosts, or opening any inbound ports.

☐ Direct

Troubleshoot

EC2 Serial Console
Access your instance's serial port for troubleshooting boot, network, and OS issues. Works without network connectivity. Requires account-level enablement.

Settings

Choose public IP address

☒ IPv4 address (43.201.18.6)

☐ IPv6 address

Username

Enter the username defined in the AMI used to launch the instance. If you didn't define a custom username, use the default username, ec2-user. Read your AMI usage instructions to check if the AMI owner has changed the default AMI username.

Connect assist – powered by AWS DevOps agent

Get help connecting to your instance by using the DevOps agent.

Connect assist

Cancel

Connect

```
sudo dnf update -y
```


```
lec2-user@ip-172-31-41-3 ~]$ sudo dnf update -y
Amazon Linux 2023 Kernel Livepatch repository
Amazon Linux 2023 Kernel Livepatch repository
s | 55 kB      00:00
Dependencies resolved.
Nothing to do.
Complete!
lec2-user@ip-172-31-41-3 ~]$
```

2. Docker 설치 (공식 apt 스크립트 필요 없음, dnf 리포에 바로 있음)

```
sudo dnf install -y docker
```

```
aws | Search [Alt+S] | cho593 (4)
IAM VPC EMR Elastic Container Service CodePipeline Aurora and RDS CloudWatch Amazon EventBridge Lambda S3 EC2 CloudFront
[ec2-user@ip-172-31-41-3 ~]$ sudo dnf install -y docker
Last metadata expiration check: 0:01:16 ago on Sun Jul 19 07:57:17 2026.
Dependencies resolved.
=====
Package                                Architecture      Version           Repository
Size
=====
Installing:
docker                                x86_64            25.0.16-1.amzn2023.0.3  amazonlinux
47 M
Installing dependencies:
container-selinux                     noarch            4:2.245.0-1.amzn2023    amazonlinux
58 k
containerd                            x86_64            2.2.5-1.amzn2023.0.1    amazonlinux
24 M
iptables-libs                         x86_64            1.8.8-3.amzn2023.0.2    amazonlinux
401 k
iptables-nft                         x86_64            1.8.8-3.amzn2023.0.2    amazonlinux
183 k
```


3. Docker 서비스 활성화 + 즉시 시작 (재부팅 시에도 자동 시작)
`sudo systemctl enable --now docker`



The screenshot shows the AWS CloudShell interface. At the top, there's a search bar and navigation icons. Below that, a row of service icons including IAM, VPC, EMR, Elastic Container Service, CodePipeline, Aurora and RDS, CloudWatch, Amazon EventBridge, Lambda, S3, EC2, and CloudFront. The terminal window shows the command `sudo systemctl enable --now docker` being executed. The output indicates that a symlink was created to enable Docker at boot time. The prompt shows the user is `ec2-user` on instance `ip-172-31-41-3`.

```
[ec2-user@ip-172-31-41-3 ~]$ sudo systemctl enable --now docker
Created symlink /etc/systemd/system/multi-user.target.wants/docker.service → /usr/lib/systemd/system/docker.service.
[ec2-user@ip-172-31-41-3 ~]$
```


4. 기본 계정(ec2-user)을 docker 그룹에 추가 (`sudo` 없이 사용)
`sudo usermod -aG docker ec2-user`



This screenshot is similar to the previous one, showing the AWS CloudShell interface. The terminal window shows the command `sudo usermod -aG docker ec2-user` being executed. The prompt shows the user is `ec2-user` on instance `ip-172-31-41-3`.

```
[ec2-user@ip-172-31-41-3 ~]$ sudo usermod -aG docker ec2-user
[ec2-user@ip-172-31-41-3 ~]$
```

5. 설치 확인
docker --version




The screenshot shows the AWS CLI interface. At the top, there is an AWS logo, a search bar with the text "Search", and a button labeled "[Alt+S]". Below this is a navigation bar with icons and labels for various AWS services: IAM, VPC, EMR, Elastic Container Service, CodePipeline, Aurora and RDS, CloudWatch, Amazon EventBridge, Lambda, S3, EC2, and CloudFront. The main terminal area displays the command `[ec2-user@ip-172-31-41-3 ~]$ docker --version` and its output: `Docker version 25.0.14, build 0bab007`. The prompt `[ec2-user@ip-172-31-41-3 ~]$` is shown again at the end of the line.

```
[ec2-user@ip-172-31-41-3 ~]$ docker --version
Docker version 25.0.14, build 0bab007
[ec2-user@ip-172-31-41-3 ~]$
```

장고 프로젝트 설치 및 실행

```
# 1. 이미지 pull
docker pull goodwon593/django-web:latest
```

A screenshot of a terminal window with the AWS CLI interface. The top bar shows the AWS logo, a search bar, and a navigation menu with icons for IAM, VPC, EMR, Elastic Container Service, CodePipeline, Aurora and RDS, CloudWatch, Amazon EventBridge, Lambda, S3, EC2, and CloudFront. The terminal text shows the command to pull a Docker image and its progress. The progress bar for the 25fee5188be1 layer is partially filled with equals signs, and the download speed is 45.85MB/139.9MB. The progress bar for the b74fd8f4ec77 layer is also partially filled, and the download speed is 68.12kB/5.741MB. The terminal text is as follows:

```
[ec2-user@ip-172-31-41-3 ~]$ docker pull goodwon593/django-web:latest
latest: Pulling from goodwon593/django-web
062e450697fa: Pull complete
cd384decb927: Pull complete
463aa101532a: Pull complete
4a633c382b06: Pull complete
25fee5188be1: Downloading [=====>] 45.85MB/139.9MB
89f7ed05ca2b: Download complete
62a3e44d4255: Download complete
466ffb8f7828: Download complete
b74fd8f4ec77: Downloading [>] 68.12kB/5.741MB
4b4648be49d6: Waiting
73071a2757b2: Waiting
6ce7f83ebd8c: Waiting
```


2. 컨테이너 실행 (nginx가 컨테이너 내부 80번에서 받아 gunicorn으로 프록시)
docker run -d --name django-server -p 80:80 goodwon593/django-web:latest



The screenshot shows an AWS CLI terminal window. The top bar includes the AWS logo, a search bar, and a list of services: IAM, VPC, EMR, Elastic Container Service, CodePipeline, Aurora and RDS, CloudWatch, Amazon EventBridge, Lambda, S3, EC2, and CloudFront. The terminal output shows the following commands and results:

```
[ec2-user@ip-172-31-41-3 ~]$ docker run -d --name django-server -p 80:80 goodwon593/django-web:latest
ld36fad1f8210a18603bc4081aee6300e6b1a522d0e4dc3249842bcdcbd7e37f
[ec2-user@ip-172-31-41-3 ~]$
[ec2-user@ip-172-31-41-3 ~]$ docker ps
```

CONTAINER ID	IMAGE	COMMAND	CREATED	STATUS	PORTS	NAMES
ld36fad1f821	goodwon593/django-web:latest	"/app/run.sh"	5 seconds ago	Up 4 seconds	0.0.0.0:80->80/tcp, :::80->80/tcp	django-server

```
[ec2-user@ip-172-31-41-3 ~]$
```

장고 웹서비스 접속

The screenshot displays the AWS Management Console interface for the 'Instances' page. The left sidebar shows the navigation menu with 'Instances' selected. The main content area shows a list of instances with one instance, 'django-web', in a 'Running' state. Below the list, the details for the instance 'i-055797a41d1ce1a78 (django-web)' are shown, including the public IPv4 address '43.201.18.6' which is highlighted and has a tooltip indicating it has been copied.

Instances (1/1) Info

Saved filter sets: Choose filter set

Find Instance by attribute or tag (case-sensitive)

Name	Instance ID	Instance state	Instance type	Status check	Availability Zone	Public IPv4 DNS	Public IPv4 ...	Elastic IP
django-web	i-055797a41d1ce1a78	Running	t3.micro	3/3 checks passed	ap-northeast-2c	ec2-43-201-18-6.ap-no...	43.201.18.6	-

i-055797a41d1ce1a78 (django-web)

Details | Status and alarms | Monitoring | Security | Networking | Storage | Tags

Instance summary Info

Instance ID: i-055797a41d1ce1a78

IPv4 address: 43.201.18.6 (Public IPv4 address copied)

Private IPv4 addresses: 172.31.41.3

Public DNS:

꼭 http로 접속해야함!

http://[Public IPv4 address]

