Informatica® Cloud Data Integration

Amplitude Connector

Informatica Cloud Data Integration Amplitude Connector
April 2026

© Copyright Informatica LLC 2023, 2026

This software and documentation are provided only under a separate license agreement containing restrictions on use and disclosure. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC.

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation is subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License.

Informatica, the Informatica logo, Informatica Cloud, and PowerCenter are trademarks or registered trademarks of Informatica LLC in the United States and many jurisdictions throughout the world. A current list of Informatica trademarks is available on the web at https://www.informatica.com/trademarks.html. Other company and product names may be trade names or trademarks of their respective owners.

Portions of this software and/or documentation are subject to copyright held by third parties. Required third party notices are included with the product.

See patents at https://www.informatica.com/legal/patents.html.

DISCLAIMER: Informatica LLC provides this documentation "as is" without warranty of any kind, either express or implied, including, but not limited to, the implied warranties of noninfringement, merchantability, or use for a particular purpose. Informatica LLC does not warrant that this software or documentation is error free. The information provided in this software or documentation may include technical inaccuracies or typographical errors. The information in this software and documentation is subject to change at any time without notice.

NOTICES

This Informatica product (the "Software") includes certain drivers (the "DataDirect Drivers") from DataDirect Technologies, an operating company of Progress Software Corporation ("DataDirect") which are subject to the following terms and conditions:

1. THE DATADIRECT DRIVERS ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESSED OR IMPLIED, INCLUDING BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NON-INFRINGEMENT.
2. IN NO EVENT WILL DATADIRECT OR ITS THIRD PARTY SUPPLIERS BE LIABLE TO THE END-USER CUSTOMER FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, CONSEQUENTIAL OR OTHER DAMAGES ARISING OUT OF THE USE OF THE ODBC DRIVERS, WHETHER OR NOT INFORMED OF THE POSSIBILITIES OF DAMAGES IN ADVANCE. THESE LIMITATIONS APPLY TO ALL CAUSES OF ACTION, INCLUDING, WITHOUT LIMITATION, BREACH OF CONTRACT, BREACH OF WARRANTY, NEGLIGENCE, STRICT LIABILITY, MISREPRESENTATION AND OTHER TORTS.

The information in this documentation is subject to change without notice. If you find any problems in this documentation, report them to us at infa_documentation@informatica.com.

Informatica products are warranted according to the terms and conditions of the agreements under which they are provided. INFORMATICA PROVIDES THE INFORMATION IN THIS DOCUMENT "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING WITHOUT ANY WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND ANY WARRANTY OR CONDITION OF NON-INFRINGEMENT.

Publication Date: 2026-10-16

Table of Contents

Preface 4

Informatica Resources 4

- Informatica Documentation 4
- IDMC web site 4
- IDMC Communities 4
- IDMC Marketplace 4
- Data Integration connector documentation 5
- Informatica Knowledge Base 5
- IDMC Trust Center 5
- IDMC Pulse Dashboard 5
- Informatica Global Customer Support 5

Chapter 1: Introduction to Amplitude Connector 6

Amplitude Connector assets 6

Chapter 2: Amplitude connections 7

Amplitude connection properties 7

Chapter 3: Amplitude operations 9

Amplitude objects and operations 9

Amplitude source operations 10

- Configuring a request using Request Message Editor 10
- Field mapping in a Source transformation 11

Chapter 4: Mappings for Amplitude 13

Amplitude Source transformation in mappings 13

- Source transformation properties 13

Chapter 5: Data type reference 15

Amplitude and transformation data types 15

Index 17

Preface

Use Amplitude Connector to learn how to read from Amplitude by using Cloud Data Integration. Learn to create an Amplitude connection, run mappings and tasks in Cloud Data Integration.

Informatica Resources

Informatica provides you with a range of product resources through the Informatica Network and other online portals. Use the resources to get the most from your Informatica products and solutions and to learn from other Informatica users and subject matter experts.

Informatica Documentation

Use the Informatica Documentation Portal to explore an extensive library of documentation for current and recent product releases. To explore the Documentation Portal, visit https://docs.informatica.com.

If you have questions, comments, or ideas about the product documentation, contact the Informatica Documentation team at infa_documentation@informatica.com.

IDMC web site

You can access the Informatica® Intelligent Data Management Cloud™ (IDMC) web site at http://www.informatica.com/cloud.

IDMC Communities

Use the IDMC Community to discuss and resolve technical issues. You can also find technical tips, documentation updates, and answers to frequently asked questions.

Access the IDMC Community at:

https://network.informatica.com/community/informatica-network/products/cloud-integration

Developers can learn more and share tips at the Cloud Developer community:

https://network.informatica.com/community/informatica-network/products/cloud-integration/cloud-developers

IDMC Marketplace

Visit the Informatica Marketplace to try and buy Data Integration Connectors, templates, and mapplets:

https://marketplace.informatica.com/

Data Integration connector documentation

You can access documentation for Data Integration Connectors at the Documentation Portal. To explore the Documentation Portal, visit https://docs.informatica.com.

Informatica Knowledge Base

Use the Informatica Knowledge Base to find product resources such as how-to articles, best practices, video tutorials, and answers to frequently asked questions.

To search the Knowledge Base, visit https://search.informatica.com. If you have questions, comments, or ideas about the Knowledge Base, contact the Informatica Knowledge Base team at KB_Feedback@informatica.com.

IDMC Trust Center

The IDMC Trust Center provides information about Informatica security, compliance, and privacy practices.

You can access the trust center at https://trust.informatica.com/.

IDMC Pulse Dashboard

The IDMC Pulse Dashboard provides system status and upgrade information for all PODs and services across IDMC.

Follow the services you use and subscribe to alerts to receive notifications about upgrades, maintenance, production incidents, and upcoming releases. The IDMC Pulse Dashboard displays the production status of all the IDMC products. All maintenance updates are posted to this page, and during an outage, it will have the most current information. To ensure you are notified of updates and outages, you can subscribe to receive updates for a single service or all IDMC services. Subscribing to all services is the best way to be certain you never miss an update.

For more information, see the Service Status and Communications guide.

Informatica Global Customer Support

You can contact a Global Support Center through the Informatica Network or by telephone.

To find online support resources on the Informatica Network, click **Contact Support** in the IDMC Help menu to go to the **Cloud Support** page. The **Cloud Support** page includes system status information and community discussions. Log in to Informatica Network and click **Need Help** to find additional resources and to contact Informatica Global Customer Support through email.

The telephone numbers for Informatica Global Customer Support are available from the Informatica web site at https://www.informatica.com/services-and-training/support-services/contact-us.html.

CHAPTER 1

Introduction to Amplitude Connector

Use Amplitude Connector to securely read data from Amplitude.

Amplitude Connector uses the Amplitude API to read hierarchical data from objects such as events, users, groups, and cohorts.

Create an Amplitude connection to read product analytics and user behavior data from Amplitude. You can use the Amplitude connection in mappings and mapping tasks.

When you run a mapping or task that uses an Amplitude connection, Data Integration reads the data from Amplitude based on the workflow and connection configuration.

Amplitude Connector assets

Create assets in Data Integration to integrate data using Amplitude Connector.

When you use Amplitude Connector, you can include the following Data Integration assets:

- Mapping
- Mapping task

For more information about configuring assets and transformations, see *Mappings*, *Transformations*, and *Tasks* in the Data Integration documentation.

CHAPTER 2

Amplitude connections

Use an Amplitude connection to access an Amplitude object.

Create an Amplitude connection to securely read data from Amplitude. You can use an Amplitude connection to specify sources in mappings and mapping tasks.

Amplitude connection properties

When you create an Amplitude connection, configure the connection properties.

The following table describes the Amplitude connection properties:

Connection property	Description
Connection Name	Name of the connection. Each connection name must be unique within the organization. Connection names can contain alphanumeric characters, spaces, and the following special characters: _ . + -, Maximum length is 255 characters.
Description	Description of the connection. Maximum length is 4000 characters.
Use Secret Vault	Stores sensitive credentials for this connection in the secrets manager that is configured for your organization. This property appears only if secrets manager is set up for your organization. When you enable the secret vault in the connection, you can select the credentials that the Secure Agent retrieves from the secrets manager. If you don't enable this option, the credentials are stored in the repository or on a local Secure Agent, depending on how your organization is configured. **Note:** If you're using this connection to apply data access policies through pushdown or proxy services, you cannot use the Secret Vault configuration option. For information about how to configure and use a secrets manager, see "Secrets manager configuration" in the Administrator help.
Runtime Environment	The name of the runtime environment where you want to run tasks. You can specify a Secure Agent, Hosted Agent, or elastic runtime environment. For more information about runtime environments, see *Runtime Environments* in the Administrator help.
API Key	The API key to access the Amplitude account.

Connection property	Description
Secret Key	The secret key of the Amplitude account.
Region Name	The data residency region where the Amplitude project data is hosted and processed. Select US or EU. The default region is US.

CHAPTER 3

Amplitude operations

Amplitude exposes the web service API that the Secure Agent uses to perform integration tasks through the REST protocol.

When you create a mapping, select an Amplitude connection and an operation in the Source transformation. Each operation corresponds to a GET endpoint in the Amplitude API. The Secure Agent uses the connection to call that endpoint and read data from Amplitude. The request and response messages contain hierarchical data in JSON format.

Amplitude objects and operations

The following table lists the GET operations you can use for Amplitude objects:

Amplitude Object	Relative Path to the Object
Average Session Length	/api/2/sessions/average
Average Sessions Per User	/api/2/sessions/peruser
Event Segmentation	/api/2/events/segmentation
Funnel Analysis	/api/2/funnels
Get All Annotation Categories	/api/3/annotation-categories
Get All Annotations	/api/3/annotations
Get All Cohorts	/api/3/cohorts
Get Annotation Category by ID	/api/3/annotation-categories/{category_id}
Get Event Categories	/api/2/taxonomy/category
Get Event Category	/api/2/taxonomy/category/{category_name}
Get Event List	/api/2/events/list
Get Event Properties	/api/2/taxonomy/event-property
Get Event Type	/api/2/taxonomy/event/{event_type}

Amplitude Object	Relative Path to the Object
Get Event Types	/api/2/taxonomy/event
Get Group Properties	/api/2/taxonomy/group-property
Get Real-time Active Users	/api/2/realtime
Get Revenue LTV	/api/2/revenue/ltv
Get Single Annotation	/api/3/annotations/{annotation_id}
Get User Activity	/api/2/useractivity
Get User Count	/api/2/users
Get User Properties	/api/2/taxonomy/user-property
Get User Property	/api/2/taxonomy/user-property/{user_property}
Retention Analysis	/api/2/retention
Search for User	/api/2/usersearch
Session Length Distribution	/api/2/sessions/length
User Composition	/api/2/composition

Amplitude source operations

Create a Source transformation in the Mapping Task wizard to read data from Amplitude.

To configure the Source operation, perform the following steps:

1. In the Source transformation, select a Amplitude connection.
2. On the **Source** tab, select an operation from the list of operations.
3. Configure the request message for the operation. Copy the request message from the sample template, and edit the JSON based on your use case.

Configuring a request using Request Message Editor

When you create a Source transformation, configure a JSON request message for the operation that you want to perform in Amplitude.

Use the **Request Message Editor** to create a request message. The request message uses the JSON format and contains request parameters exposed by the Amplitude API for a specific operation. You can use the default request message for the operation, and then customize it to specify the data that you want to include.


To customize your request, copy the request message from the sample template to the **Request Message Editor** pane where you can edit the JSON message and add the attributes for the request. Remove unnecessary tags from the request message to avoid operation failure. However, if the object requires no

parameters, specify an empty JSON object, `{}`, to pass mapping validation. You can hide the optional elements to see the required elements for the request message.

For example, to get a summary of a user's newest or oldest events, specify the user ID, limit, and direction for the `getUserActivity` operation. The following sample request message shows these parameters:

```
{
  "user" : "1625373250235",
  "limit" : 10,
  "direction" : "latest"
}
```

The following image shows the request message template and a request message configured to get a user summary along with the newest or oldest events in the Mapping Designer:



The request message format in Amplitude Connector follows the service request definition in Amplitude. Use well-formed JSON in the request message, and include the parameters that you need for your use case.


Field mapping in a Source transformation

The response message format follows the service response definition in Amplitude. You can map response fields from a hierarchical to a relational structure of output groups and fields.

After you configure an operation for a source and specify the request message, create the relational format from the hierarchical data to include groups and fields that you want in the output.

Select the elements in the response structure that you want to include as output fields. The Secure Agent converts the JSON response in the hierarchical structure to relational groups at run time.

The following image shows an example hierarchical response structure generated for the `getUserActivity` operation, and the corresponding relational output fields for the response:



You can edit the data type, precision, and scale for the groups and fields after mapping the fields.

For more information about field mapping, see *Transformations* in the Data Integration documentation.

CHAPTER 4

Mappings for Amplitude

When you create a mapping, you define the source to represent an Amplitude object. Use the Mapping Designer in Data Integration to add the Source transformation in the mapping canvas and configure the Amplitude source properties.

Amplitude Source transformation in mappings

When you configure a Source transformation, select an Amplitude connection and choose an operation to represent an Amplitude source.

Use the request message template to configure the request message in JSON format.

You can view the response structure in the field mapping. When you map elements from the response structure to the output fields, the Secure Agent creates the output groups, along with primary and foreign keys for the fields. When you deploy the mapping in a mapping task and run the task, the Secure Agent reads the data from Amplitude.

Source transformation properties

You can use one or more Source transformations in a mapping.

When you select a source, the **Properties** panel displays the following tabs:

- **General**. Configure the name and description for the source.
- **Source**. Select the connection and the operation, configure the request message in the request options, and configure the advanced source properties.
- **Field Mapping**. Map elements with the response structure to the output fields.
- **Fields**. Edit the metadata of the source fields that you want to use in the mapping.

Advanced source properties

In a mapping, you can configure a Source transformation to represent an Amplitude source. If you use the Amplitude connection in a mapping task, you can also configure advanced properties on the **Source** page of the Mapping Task wizard.

Property	Description
Tracing Level	Amount of detail that appears in the log. Use the following tracing levels: - Terse - Normal - Verbose Initialization - Verbose data Default is normal.

CHAPTER 5

Data type reference

Data Integration uses the following data types in Amplitude mappings and mapping tasks:

Amplitude native data types: Amplitude data types appear in the fields tab for Source transformations when you choose to edit metadata for the fields.

Transformation data types: Set of data types that appear in the remaining transformations. They are internal data types based on ANSI SQL92 generic data types, which Informatica Cloud uses to move data across platforms. Transformation data types appear in all transformations in a mapping.

When the Secure Agent reads source data, it converts the native data types to the comparable transformation data types before transforming the data.

Amplitude and transformation data types

The following table describes the Amplitude data types that Data Integration supports and the corresponding transformation data types:

Amplitude Native Data Type	Transformation Data Type	Range and Description
Array	Binary	1 to 65535 bytes
BigInt	Bigint	-9,223,372,036,854,775,808 to 9,223,372,036,854,775,807 Precision 19, scale 19
Binary	Binary	1 to 65535 bytes
Boolean	String	1 to 65535 characters
Decimal	Decimal	Precision 31, scale 10
Double	Double	Precision 15, scale 15
Integer	Integer	-2,147,483,648 to 2,147,483,647 Precision 12, scale 12
Long	Bigint	Precision 8, scale 8
Object	String	1 to 65535 characters

Amplitude Native Data Type	Transformation Data Type	Range and Description
String	String	1 to 65535 characters
Timestamp	Date/Time	Jan 1, 0001 00:00:00 to Dec 31, 9999 23:59:59.999999999

INDEX

A

Amplitude
  connection properties 7
Amplitude connections
  overview 7
Amplitude Connector
  assets 6
  overview 6
Amplitude data types
  overview 15

C

Cloud Application Integration community
  URL 4
Cloud Developer community
  URL 4
connections
  Amplitude 7

D

Data Integration community
  URL 4
data types
  mapping to transformation data types 15

F

field mapping
  cardinality 11
  foreign key 11
  primary key 11
  XPath expression 11

I

Informatica Global Customer Support
  contact information 5
Informatica Intelligent Data Management Cloud
  web site 4

K

Klaviyo
  Operations Overview 9

M

maintenance outages 5
mapping tasks
  overview 13

S

source
  field mapping 11
  read operations 10
  request message 10
source transformation
  advanced properties 14
  mappings 13
  properties 13
status
  IDMC 5
system status 5

T

trust site
  description 5

U

upgrade notifications 5

W

web site 4