How-To Library

Informatica

Downloading and Installing the SAP NetWeaver RFC SDK Libraries for PowerExchange for SAP NetWeaver

© Copyright Informatica LLC 2016, 2022. Informatica LLC. No part of this document may be reproduced or transmitted in any form, by any means (electronic, photocopying, recording or otherwise) without prior consent of Informatica LLC. All other company and product names may be trade names or trademarks of their respective owners and/or copyrighted materials of such owners.

Abstract

PowerExchange for SAP NetWeaver uses SAP NetWeaver RFC SDK libraries to integrate with SAP. To configure PowerExchange for SAP NetWeaver, you must download the SAP NetWeaver RFC SDK libraries from the SAP Marketplace and install them. This article explains how to download the SAP NetWeaver RFC SDK libraries from the SAP Marketplace and install them.

Supported Versions

- PowerExchange for SAP NetWeaver 10.2 or later

Table of Contents

Overview. 2
Downloading the SAP NetWeaver RFC SDK Libraries from the SAP Marketplace. 2
Installing the SAP NetWeaver RFC SDK Libraries 6

Overview

PowerExchange for SAP NetWeaver uses SAP NetWeaver RFC SDK libraries to integrate with SAP. To configure PowerExchange for SAP NetWeaver, you must download the SAP NetWeaver RFC SDK libraries from the SAP Marketplace. The libraries that you need to download and install vary based on the operating system that you use.

After you download the libraries, you must copy them to the Informatica installation directories and set the required permissions for the libraries.


Downloading the SAP NetWeaver RFC SDK Libraries from the SAP Marketplace

To download the SAP NetWeaver RFC SDK libraries from the SAP Marketplace, perform the following steps:

1. Go to the SAP Service Marketplace: http://service.sap.com/support
2. Enter your SAP Service Marketplace user name and password.


   The **SAP Support Portal** page appears.
3. Click the **Download Software** icon.

The following image shows the **Download Software** icon:




4. Click the **Support Packages & Patches** tab.

   The following image shows the **Support Packages & Patches** tab:




5. Click **By Category** from the list.

   The following image shows the **By Category** option:




6. Click **Additional Components** from the list.

The following image shows the **Additional Components** option:




7. Click **SAP NW RFC SDK** from the list.

   The following image shows the **SAP NW RFC SDK** option:




8. Click **SAP NW RFC SDK 7.20**.

The following image shows the **SAP NW RFC SDK** option:



9. Select the operating system for which you want to download the SAP NetWeaver RFC SDK libraries.

   The available patches for the selected operating system appear. The following image shows the patches for Windows 64-bit operating systems:



10. Click the hyperlinked `.SAR` file to download the **SAP NW RFC SDK 7.20** libraries.

    The following image shows the hyperlinked `.SAR` file:



11. Open the command prompt and enter the following command to extract the downloaded files:

    `sapcar.exe -xvf <SAR file path>`

    For example, enter `sapcar.exe -xvf NWRFC_40-20004568.SAR`

    The SAP NetWeaver RFC SDK 7.20 libraries are extracted to the following directory:

    `<ExtractedFolder>\nwrfcsdk\lib`

    The following image shows the extracted SAP libraries in a specific folder:



Installing the SAP NetWeaver RFC SDK Libraries

To install the SAP NetWeaver RFC SDK Libraries, perform the following steps:

1. Copy the SAP NetWeaver RFC SDK libraries to the following directory:

   `<Informatica Installation Directory>\server\bin`

2. Copy the Windows 32-bit client files to the following directory:

   `<Informatica Installation Directory>\client\bin`

3. Set the following permissions for each SAP NetWeaver RFC SDK library:

   - Read, write, and execute permissions for the current user

   - Read and execute permissions for all other users

4. Download the `libsapu16_mt.so` library from the `SAPEXE.SAR` or `UCLIB.SAR` package that is available as part of the SAP kernel. You need to download the `libsapu16_mt.so` library only if you use the UNIX or Linux operating systems.

5. Copy the `libsapu16_mt.so` library to the following directory:

   `<Informatica Installation Directory>\server\bin`

Author

Subhashree Salam

Acknowledgements

The authors would like to acknowledge Praveen Kumar J, for his technical assistance with this article.