

### Арестов Никита ИС223

## 1. Создал сеть и установил DHCP на каждом пк



# 2. Настроил днс-сервер



#### 3.Перешёл к конфигруации роутера0 и роутера1

```
Router(config) #ip dhcp excluded-address 192.168.1.100
Router(config) #ip dhcp pool net1
Router(dhcp-config) #net 192.168.1.100
% Incomplete command.
Router(dhcp-config) #net 192.168.1.100 255.255.255.0
Router(dhcp-config) #default-router 192.168.1.100
Router(dhcp-config) #dns-server 192.168.2.101
Router(dhcp-config) #int fa0/0
Router(config-if) #ip adress 192.168.1.100 255.255.255.0
% Invalid input detected at '^' marker.
Router(config-if) #ip address 192.168.1.100 255.255.255.0
Router(config-if) #no sh
Router(config-if) #int fal/0
Router(config-if) #ip address 192.168.3.1 255.255.255.0
Router(config-if) #no sh
Router(config-if) #ro rip
Router(config-router) #net 192.168.1.0
Router(config-router) #net 192.168.3.0
Router(config-router) #exit
Router(config) #wr mem
% Invalid input detected at '^' marker.
Router (config) #exit
Router#
%SYS-5-CONFIG I: Configured from console by console
wr mem
Building configuration...
[OK]
Router#
```

```
Router>en
Router#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config) #ip dhcp excluded-address 192.168.2.100 192.168.2.101
Router(config) #ip dhcp pool net2
Router(dhcp-config) #net 192.168.2.0 255.255.255.0
Router(dhcp-config) #default-router 192.168.2.100
Router(dhcp-config) #dns-server 192.168.2.101
Router(dhcp-config)#int fa0/0
Router(config-if) #ip ad 192.168.2.100 255.255.255.0
Router(config-if) #no sh
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
int fal/0
Router(config-if) #ip ad 192.168.3.2 255.255.255.0
Router(config-if) #no sh
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed state to up
Router(config-router) #net 192.168.2.0
Router(config-router) #net 192.168.3.0
Router(config-router) #exit
Router (config) #exit
Router#
%SYS-5-CONFIG_I: Configured from console by console
wr mem
Building configuration ...
LOK1
Router#
```

### 4. Проверка

```
Packet Tracer PC Command Line 1.0
C:\>ping 169.254.81.200

Pinging 169.254.81.200 with 32 bytes of data:

Reply from 192.168.1.100: Destination host unreachable.

Ping statistics for 169.254.81.200:

Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>
```