



TASK – 10

keep an EC2 root volume after terminating the instance.



Step 1 – Create instance

1. Open EC2 → Launch instance.
2. Enter instance name.
3. Select the AMI.
4. Choose the instance type.




Step 2 – Configure storage

1. Go to the Configure storage section.
2. Expand the root volume settings.
3. Delete on termination set it to No.
4. Continue and launch the instance.



Step 3 – Terminate instance

1. After use, go to EC2 → Instances.
2. Select instance → click Instance state → Terminate.



The screenshot displays the AWS Management Console interface for the EC2 service. The left-hand navigation pane shows the 'Instances' section under the 'EC2' category. The main content area shows a list of instances. The instance 'Sever2' with ID 'i-0c1c8161531db94e6' is selected. The instance state is 'Terminated'. The instance type is 't2.micro'. The instance is located in the 'us-east-1c' availability zone. The instance summary shows the instance ID, public IPv4 address, private IPv4 addresses, IPv6 address, instance state, public DNS, and hostname type.

Name	Instance ID	Instance state	Instance type	Status check	Alarm status	Availability Zone
sever	i-065608f6233b49497	Terminated	t2.micro	-	View alarms +	us-east-1c
Sever2	i-0c1c8161531db94e6	Terminated	t2.micro	-	View alarms +	us-east-1b

i-0c1c8161531db94e6 (Sever2)

Details | Status and alarms | Monitoring | Security | Networking | Storage | Tags

Instance summary

Instance ID i-0c1c8161531db94e6	Public IPv4 address -	Private IPv4 addresses -
IPv6 address -	Instance state Terminated	Public DNS -
Hostname type -		

Step 4 – Check volume

1. Go to EC2 → Volumes.
2. Confirm the root volume (8 GB) is still in Available state.

The screenshot shows the AWS Management Console interface for the 'us-east-1' region. The left sidebar contains navigation links for EC2, IAM, S3, and other services. The main content area displays the 'Volumes (1/1)' page. A table lists the volume 'vol-05163a749f5d980e5' with a size of 8 GiB and a status of 'Available'. Below the table, the 'Details' tab for the volume is expanded, showing various attributes such as 'Volume ID', 'Size', 'Type', 'IOPS', 'Throughput', 'Status check', 'Created', 'Availability Zone', 'Managed', and 'Operator'.

Name	Volume ID	Type	Size	IOPS	Throughput	Snapshot ID	Created
☒	vol-05163a749f5d980e5	gp3	8 GiB	3000	125	snap-0f9367e...	2025/09/09 15:01 GMT

Volume ID: vol-05163a749f5d980e5			
Details	Status checks	Monitoring	Tags
Volume ID vol-05163a749f5d980e5	Size 8 GiB	Type gp3	Status check Okay
AWS Compute Optimizer finding Opt-in to AWS Compute Optimizer for recommendations. Learn more	Volume state Available	IOPS 3000	Throughput 125
Fast snapshot restored No	Availability Zone us-east-1b	Created Tue Sep 09 2025 15:01:56 GMT+0530 (India Standard Time)	Multi-Attach enabled No
Attached resources	Outposts ARN	Managed	Operator