
Real Time Movie booking Application

Landing page:



Display the movie list in a carousel that moves to the next slide on its own.


If the user hovers over a movie, the carousel movement should pause. The carousel should also include buttons to move to the next and previous slides, and there should be small Instagram-like dots to indicate the slides.

When the user clicks the 'Book Movie' button:

- a) If the user isn't logged in, they'll be directed to a login/register form (you can find the form on the next page).
- b) If the user is already logged in, they'll be taken to the seat booking page to choose and book seats.

NOTE: All pages will have a header with the user name and logout button (if logged in) or a login button.

Authentication:



User Login Form:

Users have the option to log in using either their email address or phone number.

Upon clicking the login button, make sure to implement thorough validation checks to ensure that the entered login credentials are valid.

User Registration form:

Create a registration form with these fields: Email Address, Phone Number, Password and Confirm Password.

Ensure accurate form validation when users click the "Register" button. This includes:

- Checking the email format.
- Validating the phone number.
- Verifying that the password:
 - Contains at least one uppercase letter
 - Contains at least one lowercase letter
 - Has one special character
 - It Is at least 8 characters long.
- Confirming that the "Password" and "Confirm Password" entries match.
- Displaying clear error messages on error.

Seat selection:



Show a seating layout with 6 rows and 10 columns. The last two rows should have higher prices than the previous rows.

Distinguish seats using colors:

- Gray for booked seats
- Green for selected seats
- White for available seats


When a user picks seats:

- Show a "Pay Now" button with the total cost.
- Clicking it displays a payment popup (see next page for reference).

After clicking "Pay Now" and starting payment:

• The chosen seats should be temporarily on hold.

Payment:



Show the seat IDs that the user selected and the total cost.

When confirming the booking:

- Set a 60-second timer.
- If the timer ends, redirect the user to the main page and clear selected seats.

After clicking the "Confirm Booking" button:

- Display an alert message.
- Redirect the user to the main page.

After clicking the "Cancel Booking" button:

• Redirect the user to the main page and clear the selected seats.