	Laptop Windows 11		Android Smartphone
https://rikkyhype.com/ua	Microsoft Edge 121.0.2277.98	Firefox122.0	Chrome
Header			
Logo			
"Winter collection sale" button			
Categories button			
Change the language			
Personal cabinet			
Cart			
Main page body			
Banner carusel			
New section carusel			
New section - redirect to PDP			
New section - Add to wishlist button			
Sale section - redirect to PDP			
Report on humanitarian aid - redirect to PDP			
Categories section carusel			
Categories section - Female			
Categories section - Male			
Categories section - redirect to PDP			
Inform block			
Inform block - "Get to know the brand" button			
Footer			
Subscribe section			
Subscribe functionality			
Social media links and buttons			
Logo			
Contact phone			

Store links		
Copyright		

	Name	Preconditions	Steps	Expected result	Postconditions
	1 Logo on the main page	The main page should be opened.	Look at the middle of the top of the header.	Company logo is displayed acording to design.	
			Hover the cursor on the logo.	Pointer cursor.	
			Click the logo.	The main page is reloaded.	
			Open some some other page. And click the logo.	The main page is opened.	
·	"Winter collection sale" 2 button	The main page should be opened.	Look at the "Winter collection sale" button at the middle of the top of the header.	"Winter collection sale" button is available.	
			Hover cursor at the "Winter collection sale" button.	Pointer cursor.	
			Click the "Winter collection sale" button.	A new page with "Sale" content is opened.	
:	Country/language switcher functionality	The main page should be opened.	Look at the top right corner of the page and find Country/Language switcher.	The language switcher is available. Ukraine/Ukrainian by default.	
			Hower cursor to the Country/Language switcher.	Pointer cursor.	
			Click the Country/language switcher.	Pop-up is opened with two sections. Ukraine and Ukrainian by default.	
			Click the "Ukraine" section.	Drop down list is opened with two options "Ukraine" and "Poland".	
			Select "Poland".	The country switcher is changed to "Poland" and the language switcher is changed to "Polish".	
			Click the "Apply" button.	The page is loaded in Polish.	
,	Personal cabinet button functionality	The main page should be opened.	Look at the top right corner of the page and find Personal cabinet button.	The personal cabinet button is available.	
			Hover cursor to the Personal cabinet button.	Pointer cursor.	

				Click the Personal cabinet button.	A "Personal cabinet" page is loaded.	
	5	Cart button functionality	The main page should be opened.	Look at the top right corner of the page and find Cart button.	The cart button is available.	
				Hover cursor to the cart button.	Pointer cursor.	
				Click the cart button.	A "My cart" pop-up is opened.	
ID		Name	Preconditions	Steps	Expected result	Postconditions
	1	Autorization to the "Personal cabinet"	The "Personal cabinet" page should be loaded.	Hover cursor to the input field.	Text pointer appears.	
				Enter the invalid data.	The input field turns red, which indicates an input error.	
	2	Subscription to the newsletter	The main page is opened.	Hover cursor to the input field at the lower right corner of the footer.	Text pointer appears.	
				Enter the invalid data.	The input field turns red and an error notification appears.	
	3	Adding the product to wishlist without autorization	The PDP with any product is opened.	Hover cursor to the wishlist button at the top right corner of the page.	Pointer cursor.	
				Click on the wishlist button.	The pop-up with the autorization is opened.	
	4	Adding the product to cart without selecting a size	The PDP with any product is opened.	Hover cursor to the "Add to cart" button.	Pointer cursor.	
				Click on the "Add to cart" button.	An error notification appears highlighting the "Size" buttons.	
	5	Entering delivery data	The "My cart" page with any selected product is opened.	Hover cursor to the "Place an order" button at the lower right corner of the page.	Pointer cursor.	
				Click on the "Place an order" button.	The "Order placement" page is loaded.	
				Enter the invalid data to the 4 input fields.	Input fields turn red and notification errors appear.	