MarineLife Mega Pack



Dear customers,

Thank you for purchasing our asset pack, MarineLife Mega Pack. Your support means the world to us and motivates us to continue improving our products.

We hope you've found value and inspiration for your projects with our asset pack in hand. Your feedback and creative use of our resources are incredibly valuable to us, helping us constantly refine our offerings.

Please don't hesitate to reach out with any questions, ideas, or feedback you'd like to share. Your satisfaction is our priority, and we're here to provide all the support you need.

Once again, thank you for your purchase and trust in our products. We look forward to seeing your future projects and collaborating with you.

Best regards,

LittleSimple

How to convert project to URP

Items like the water shader or post-processing effecta and volumes, which were used to capture the promotional images, don't function with the Default Render Pipeline. Converting the project to URP is necessary. Let's explore some options around this.

Step 1.

Go to Edit > Project Settings > Graphics

Click *Scriptable Render Pipeline Settings* and select *URP.*

Step 2.

Go to Edit > Project Settings > Quality

Click *Render Pipeline Asset* and select *URP.*

Step 3.

Go to Window > Rendering > Render Pipeline Converter Check all the boxes and click *Initialize And Convert*




Project Settings
Adaptive Performance
Asset Store Tools
Audio
Burst AOT Settings
Editor
Graphics
URP Global Settings
Input Manager
Memory Settings
Package Manager
Physics
Physics 2D
Player
Preset Manager
Quality
Scene Template
Script Execution Order
Services
ShaderGraph
Tags and Layers
TextMesh Pro
Time
Timeline
UI Builder
Version Control
Visual Scripting
XR Plugin Management
Graphics
Scriptable Render Pipeline Settings
URP (Universal Render Pipeline Asset)
A Scriptable Render Pipeline is in use, some settings will not be used and are hidden
Built-in Shader Settings
Video
Always Include
Always Included Shaders
Size
6
Element 0
Legacy Shaders/Diffuse
Element 1
Hidden/CubeBlur
Element 2
Hidden/CubeCopy
Element 3
Hidden/CubeBlend
Element 4
Sprites/Default
Element 5
UI/Default
Shader Stripping
Lightmap Modes
Automatic
Fog Modes
Automatic
Instancing Variants
Strip Unused
BatchRendererGroup Variants
Strip if no Hybrid Renderer package
Shader Loading
Log Shader Compilation
Renderer Light Probe Selection
Find closest Light Probe
Preloaded Shaders
Size
0
Preload shaders after showing first scene
Currently tracked: 33 shaders 84 total variants
Save to asset...
Clear
Culling Settings
Camera-Relative Culling
Lights
Shadows


Render Pipeline Converter
Built-in to URP
This tool converts project elements from the Built-in Render Pipeline to URP.
This process makes irreversible changes to the project. Back up your project before proceeding.
Click the converters below to see more information.
Rendering Settings
0/0 selected
Pending Initialization
0 – 0 0 0
This converter will look at creating Universal Render Pipeline assets and respective Renderer Assets and configure their settings based on equivalent settings from builtin renderer.
Material Upgrade
0/0 selected
Pending Initialization
0 – 0 0 0
This converter converts Materials from the Built-in Render Pipeline to URP. This converter works best on default pre-built Materials that are supplied by Unity. Custom Materials are not supported.
Animation Clip Converter
0/0 selected
Pending Initialization
0 – 0 0 0
This converter updates all animation clips so that they reference the correct Materials.
Readonly Material Converter
0/0 selected
Pending Initialization
0 – 0 0 0
Converts references to Built-In readonly materials to URP readonly materials. This will create temporarily a .index file and that can take a long time.
Initialize Converters
Initialize And Convert

How to use the models

Discover our meticulously organized collection of models, neatly sorted into categories within the designated direktory –

LittleSimple > MarineLife Mega Pack > Prefabs. **For seamless integration into your projects, we've ensured that all models are easily accessible for drag-and-drop directly into your scenes. Please avoid utilizing models from the 'Imports' directory to maintain consistency and optimal performance. Enhance your workflow with our intuitive asset organization, designed to streamline your creative process.**

How to use the skyboxes

Located within the designated folder path *LittleSimple > MarineLife Mega Pack > MaterialsAndShaders > SkyBoxMaterials,* simply drag and drop the skybox onto your scene background or go to *Window > Rendering > Lighting > Environment > SkyBox* Material and drag and drop the skybox material there.

How to use the scripts

1. **Locate the scripts**
   LittleSimple > MarineLife Mega Pack > Scripts

2. **Create an empty GameObject and place it in the scene. This GameObject will serve as the basic container for your fish swarm. Add the „GlobalFlock“ script and adjust the size and number of fish in the swarm according to your preferences. This step allows you to precisely define how your swarm will move and interact within the scene.**

3. **Afterward, add the desired fishPrefab to the script, ensuring that the fishPrefab has the „Flock“ script component attached. This step is crucial for the proper functioning of the system. (Tropical fish 1-4 already has the Flock Script set up)**

4. **Flock settings:**
   -Speed (move speed of the fish)
   -RotationSpeed (rotation speed of the fish)
   -Rand speed (returns random valuve between maximum and minimum speed, if this is checked make sure to assign the minimum and maximum speed)
   -Neighbour Distance (The distance required for a fish to join the flock)
   -Avoiding Distance (The distance at which fish start to avoid each other)

5. **Enjoy**