# Change Disk Size while Allocated\_Disk Mgmt

Last updated by | Kevin Gregoire | Mar 29, 2022 at 11:47 AM PDT

Tags		
cw.Disk-Mgmt	cw.TSG	

#### **Contents**

- Summary
- Error Details
- Cause
- Resolution
- Need additional help or have feedback?

## **Summary**

Use this TSG to determine RCA for why a customer could not update their disks

### **Error Details**

{ "innererror": { "internalErrorCode": "ChangeDiskSizeWhileAttachedNotAllowed" }, "code": "OperationNotAllowed", "message": "Cannot resize disk DISKNAME while it is attached to running VM /subscriptions/SubID/resourceGroups/MC\_alpha-k8s-resource-group\_tdy-k8s-

alpha\_australiaeast/providers/Microsoft.Compute/virtualMachines/VMNAME. Resizing a disk of an Azure Virtual Machine requires the virtual machine to be deallocated. Please stop your VM and retry the operation."

#### Cause

The customer is attempting to resize the disk while while the VM that the disk is attached to is still allocated

## Resolution

Customer needs to either deallocate the VM or detach the disk in order to resize the disk.

# Need additional help or have feedback?

To engage the Disk Management SMEs	To provide feedback on this page	To provide kudos on this page
Please reach out to the <a href="Disk Management">Disk Management</a> <a href="SMEs">SMEs</a> <a href="Disk Management">Disk Management</a> <a href="Disk Management">SMEs</a> <a href="Disk Management">Disk Management</a> <a href="Disk Management">D</a>	Use the <b>Disk Management Feedback</b> form to submit detailed feedback on improvements or new content ideas for Disk Management.	Use the <b>Disk Management Kudos</b> form to submit kudos on the page. Kudos will help us improve our wiki content overall!
Make sure to use the <b>Ava process</b> for faster assistance.	<b>Please note</b> the link to the page is required when submitting feedback on existing pages! If it is a new content idea, please put N/A in the Wiki Page Link.	<b>Please note</b> the link to the page is required when submitting kudos!