WikipediA

Phase (matter)

In the <u>physical sciences</u>, a **phase** is a region of space (a <u>thermodynamic system</u>), throughout which all physical properties of a material are essentially uniform. Examples of physical properties include <u>density</u>, <u>index of refraction</u>, <u>magnetization</u> and chemical composition. A simple description is that a phase is a region of material that is chemically uniform, physically distinct, and (often) mechanically separable. In a system consisting of ice and water in a glass jar, the ice cubes are one phase, the water is a second phase, and the humid air is a third phase over the ice and water. The glass of the jar is another separate phase. (See state of matter § Glass)

The term *phase* is sometimes used as a synonym for <u>state of matter</u>, but there can be several <u>immiscible</u> phases of the same state of matter. Also, the term *phase* is sometimes used to refer to a set of equilibrium states demarcated in terms of state variables such as pressure and temperature by a <u>phase boundary</u> on a <u>phase diagram</u>. Because phase boundaries relate to changes in the organization of matter, such as a change from liquid to solid or a more subtle change from one crystal structure to another, this latter usage is similar to the use of "phase" as a synonym for state of matter. However, the state of matter and phase diagram usages are not <u>commensurate</u> with the formal definition given above and the intended meaning must be determined in part from the context in which the term is used.

Contents

Types of phases

Phase equilibrium

Number of phases

Interfacial phenomena

Crystal phases

Phase transitions

Phases out of equilibrium

See also

Notes

References

External links




A small piece of rapidly melting argon ice shows the transition from solid to liquid.

Types of phases

Distinct phases may be described as different <u>states of matter</u> such as <u>gas</u>, <u>liquid</u>, <u>solid</u>, <u>plasma</u> or <u>Bose–Einstein</u> condensate. Useful mesophases between solid and liquid form other states of matter.

Distinct phases may also exist within a given state of matter. As shown in the diagram for iron alloys, several phases exist for both the solid and liquid states. Phases may also be differentiated based on <u>solubility</u> as in polar (hydrophilic) or non-polar (hydrophobic). A mixture of water (a polar liquid) and oil (a non-polar liquid) will spontaneously separate into two phases. Water has a very low <u>solubility</u> (is insoluble) in oil, and oil has a low solubility in water. Solubility is the maximum amount of a solute that can dissolve in a solvent before the solute ceases to dissolve and remains in a separate phase. A mixture can separate into more than two liquid phases and the concept of phase separation extends to solids, i.e., solids



Iron-carbon phase diagram, showing the conditions necessary to form different phases

can form <u>solid solutions</u> or crystallize into distinct crystal phases. Metal pairs that are mutually soluble can form <u>alloys</u>, whereas metal pairs that are mutually insoluble cannot.

As many as <u>eight immiscible liquid phases</u> have been observed. [a] Mutually immiscible liquid phases are formed from water (aqueous phase), hydrophobic organic solvents, perfluorocarbons (<u>fluorous phase</u>), silicones, several different metals, and also from molten phosphorus. Not all organic solvents are completely miscible, e.g. a mixture of <u>ethylene glycol</u> and <u>toluene</u> may separate into two distinct organic phases. [b]

Phases do not need to macroscopically separate spontaneously. <u>Emulsions</u> and <u>colloids</u> are examples of immiscible phase pair combinations that do not

physically separate.

Phase equilibrium

Left to equilibration, many compositions will form a uniform single phase, but depending on the temperature and pressure even a single substance may separate into two or more distinct phases. Within each phase, the properties are uniform but between the two phases properties differ.

Water in a closed jar with an air space over it forms a two phase system. Most of the water is in the liquid phase, where it is held by the mutual attraction of water molecules. Even at equilibrium molecules are constantly in motion and, once in a while, a molecule in the liquid phase gains enough kinetic energy to break away from the liquid phase and enter the gas phase. Likewise, every once in a while a vapor molecule collides with the liquid surface and condenses into the liquid. At equilibrium, evaporation and condensation processes exactly balance and there is no net change in the volume of either phase.

At room temperature and pressure, the water jar reaches equilibrium when the air over the water has a humidity of about 3%. This percentage increases as the temperature goes up. At 100 °C and atmospheric pressure, equilibrium is not reached until the air is 100% water. If the liquid is heated a little over 100 °C, the transition from liquid to gas will occur not only at the surface, but throughout the liquid volume: the water boils.

Number of phases


For a given composition, only certain phases are possible at a given <u>temperature</u> and pressure. The number and type of phases that will form is hard to predict and is usually determined by experiment. The results of such experiments can be plotted in phase diagrams.

The phase diagram shown here is for a single component system. In this simple system, which phases that are possible depends only on <u>pressure</u> and <u>temperature</u>. The markings show points where two or more phases can co-exist in equilibrium. At temperatures and pressures away from the markings, there will be only one phase at equilibrium.

In the diagram, the blue line marking the boundary between liquid and gas does not continue indefinitely, but terminates at a point called the <u>critical point</u>. As the temperature and pressure approach the critical point, the properties of the liquid and gas become progressively more similar. At the critical point, the liquid and gas become indistinguishable. Above the critical point, there are no longer separate liquid and gas phases: there is only a generic fluid phase referred to as a <u>supercritical fluid</u>. In water, the critical point occurs at around 647 K (374 °C or 705 °F) and 22.064 MPa.

An unusual feature of the water phase diagram is that the solid—liquid phase line (illustrated by the dotted green line) has a negative slope. For most substances, the slope is positive as exemplified by the dark green line. This unusual feature of water is related to ice having a lower density than liquid water. Increasing the pressure drives the water into the higher density phase, which causes melting.

Another interesting though not unusual feature of the phase diagram is the point where the solid-liquid phase line meets the liquid-gas phase line. The intersection is referred to as the <u>triple point</u>. At the triple point, all three phases can coexist.



A typical phase diagram for a single-component material, exhibiting solid, liquid and gaseous phases. The solid green line shows the usual shape of the liquid–solid phase line. The dotted green line shows the anomalous behavior of water when the pressure increases. The triple point and the critical point are shown as red dots.

Experimentally, the phase lines are relatively easy to map due to the interdependence of temperature and pressure that develops when multiple phases forms. See <u>Gibbs' phase rule</u>. Consider a test apparatus consisting of a closed and well insulated cylinder equipped with a piston. By charging the right amount of water and applying heat, the system can be brought to any point in the gas region of the phase diagram. If the piston is slowly lowered, the system will trace a curve of increasing temperature and pressure within the gas region of the phase diagram. At the point where gas begins to condense to liquid, the direction of the temperature and pressure curve will abruptly change to trace along the phase line until all of the water has condensed.

Interfacial phenomena

Between two phases in equilibrium there is a narrow region where the properties are not that of either phase. Although this region may be very thin, it can have significant and easily observable effects, such as causing a liquid to exhibit <u>surface tension</u>. In mixtures, some components may preferentially move toward the interface. In terms of modeling, describing, or understanding the behavior of a particular system, it may be efficacious to treat the interfacial region as a separate phase.

Crystal phases

A single material may have several distinct solid states capable of forming separate phases. Water is a well-known example of such a material. For example, water \underline{ice} is ordinarily found in the hexagonal form $\underline{ice} I_h$, but can also exist as the cubic $\underline{ice} I_c$, the <u>rhombohedral ice</u> II, and many other forms. <u>Polymorphism</u> is the ability of a solid to exist in more than one crystal form. For pure chemical elements, polymorphism is known as <u>allotropy</u>. For example, <u>diamond</u>, <u>graphite</u>, and fullerenes are different allotropes of carbon.

Phase transitions

When a substance undergoes a phase transition (changes from one <u>state of matter</u> to another) it usually either takes up or releases energy. For example, when water evaporates, the increase in kinetic energy as the evaporating molecules escape the attractive forces of the liquid is reflected in a decrease in temperature. The energy required to induce the phase transition is taken from the internal thermal energy of the water, which cools the liquid to a lower temperature; hence evaporation is useful for cooling. See <u>Enthalpy of vaporization</u>. The reverse process, condensation, releases heat. The heat energy, or enthalpy, associated with a solid to liquid transition is the <u>enthalpy of fusion</u> and that associated with a solid to gas transition is the enthalpy of sublimation.

Phases out of equilibrium

While phases of matter are traditionally defined for systems in thermal equilibrium, work on quantum <u>many-body</u> <u>localized</u> (MBL) systems has provided a framework for defining phases out of equilibrium. MBL phases never reach thermal equilibrium, and can allow for new forms of order disallowed in equilibrium via a phenomenon known as <u>localization protected quantum order</u>. The transitions between different MBL phases and between MBL and thermalizing phases are novel dynamical phase transitions whose properties are active areas of research.

See also

- Interface (matter)
- Phase boundary
- Literature of phase boundaries

Notes

- a. One such system is, from the top: mineral oil, silicone oil, water, aniline, perfluoro(dimethylcyclohexane), white phosphorus, gallium, and mercury. The system remains indefinitely separated at 45 °C, where gallium and phosphorus are in the molten state. From Reichardt, C. (2006). Solvents and Solvent Effects in Organic Chemistry. Wiley-VCH. pp. 9–10. ISBN 978-3-527-60567-5.
- b. This phenomenon can be used to help with catalyst recycling in <u>Heck vinylation</u>. See Bhanage, B.M.; et al. (1998). "Comparison of activity and selectivity of various metal-TPPTS complex catalysts in ethylene glycol toluene biphasic Heck vinylation reactions of iodobenzene". <u>Tetrahedron Letters</u>. 39 (51): 9509–9512. <u>doi:10.1016/S0040-4039(98)02225-4</u> (https://doi.org/10.1016%2FS0040-4039%2898%2902225-4).

References

- 1. Modell, Michael; Robert C. Reid (1974). *Thermodynamics and Its Applications*. Englewood Cliffs, NJ: Prentice-Hall. ISBN 978-0-13-914861-3.
- 2. Enrico Fermi (25 April 2012). Thermodynamics. Courier Corporation. ISBN 978-0-486-13485-7.
- 3. Clement John Adkins (14 July 1983). *Equilibrium Thermodynamics*. Cambridge University Press. <u>ISBN</u> <u>978-0-521-</u>27456-2.

External links

French physicists find a solution that reversibly solidifies with a *rise* in temperature (http://physicsweb.org/articles/new s/8/9/15/1) – α-cyclodextrin, water, and 4-methylpyridine