Michael Kepple
Operating Systems
Lab 11

#2 - **Write a "one line pipeline"**
- **"ls -l /dev | awk '{print $5}' | tr -d ',' | sort -n | uniq"**

#4 - **/dev/zero**
- What happens when you output to /dev/zero? It acts as a sink, succeeding with no other effects. Essentially used to re-route output away from STDOUT.
- What happens when you read from it? Will **return** an infite sequence of zero bits, unless a size **if** specified (using dd **for** instance).

Modify:
What I did:
To make it output all **'1'** bits:
1) edited memory.c in /usr/src/drivers/memory
Diff output:
349c349
< **if** ((s = sys_safememset(endpt, grant, 0, **'\0'**, count)) != OK)

> **if** ((s = sys_safememset(endpt, grant, 0, -1, count)) != OK)
2) make install
3) service refresh memory

To make it output '0101010..."
1) edited memory.c in /usr/src/drivers/memory
Diff output:
349c349
< if ((s = sys_safememset(endpt,grant, 0, '\0', count)) != OK)

> if ((s = sys_safememset(endpt, grant, 0, 1431655765, count)) != OK)
2) make install
3) service refresh memory

To make it output all zeroes again:
1) restored my old copy of memory.c
2) make install
3) service refresh memory

 # 5 - The "Hello, World" **Device Driver**
What I did:
Disply greeting in UPPERCASE:
1) edited hello.h in /usr/src/drivers/hello
Diff output:
5c5
< #define HELLO_MESSAGE "Hello, World!\n"

> #define HELLO_MESSAGE "HELLO, WORLD!\n"
2) make install
3) service refresh hello

Remove debug output:
1) edited hello.c in /usr/src/drivers/hello
Diff output:
47d46
< **printf(**"hello_open(). Called %d time(s).\n"**, ++open_counter);**
53d51
< **printf(**"hello_close()\n"**);**
70d67
< **printf(**"hello_transfer()\n"**);**
2) make install
3) service down hello
4) service up /usr/sbin/hello -dev /dev/hello

#6 - Magic Eight Ball Device Driver
- Minix won’t let me SSH to student right now. As soon as I figure out the connection issues I can print out copies of my code.

#7 - Writing to the "Hello, World!**" device driver**
- See above