PRACTICAL 6

AIM - To implement HTTP using a web server in Cisco Packet Tracer and access a webpage from client computers through a switch.


Introduction

HTTP stands for Hypertext Transfer Protocol. It is used for communication between a web browser and a web server.

In this practical, Server0 is configured as a web server. The client computer accesses the webpage using the server's IP address.

Requirements

1. Cisco Packet Tracer
2. Switches
3. 2 PCs
4. Copper cables as required
5. 1 server-PT



IP Address Configuration


PC0: IP Address: 192.168.1.1, Subnet mask 255.255.255.0.

PC1: IP Address: 192.168.1.2, Subnet mask 255.255.255.0


SERVER-PT: IP Address: 192.168.1.3, Subnet mask 255.255.255.0

Procedure

- Connect PC0 to Switch0.
- Connect PC1 to Switch0.
- Use Copper Straight-Through cables to connect switches to server-PT.
- Assign the required IP addresses to all the PCs.
- open Server0 and go to Desktop → IP Configuration. Select the Static option and enter the IP address 192.168.1.3 with the subnet mask 255.255.255.0
- open Server0 and go to Services → HTTP. Turn the HTTP service ON and make sure the index.html file is available.



- open PC0, go to Desktop → Web Browser, and enter http://192.168.1.3 in the address bar. Click Go and the webpage hosted on Server0 will be displayed.



Observation

The HTTP service was enabled on Server0, and the webpage was successfully opened from PC0 using the server's IP address. This confirmed that the client and web server were communicating properly.

Result

The HTTP service was successfully configured in Cisco Packet Tracer. The client PC was able to connect to Server0 and access the webpage using the server's IP address.

PRACTICAL 7


AIM - To implement FTP using a server in Cisco Packet Tracer and perform file upload and download between a client computer and the FTP server.

Introduction

FTP stands for File Transfer Protocol. It is used to transfer files between a client computer and a server. In this practical, Server0 is configured as an FTP server, and the client PC is used to upload and download a file.

Requirements

1. Cisco Packet Tracer
2. Switches
3. 2 PCs
4. Copper cables as required
5. 1 server-PT



IP Address Configuration


PC0: IP Address: 192.168.1.1, Subnet mask 255.255.255.0.

PC1: IP Address: 192.168.1.2, Subnet mask 255.255.255.0


SERVER-PT: IP Address: 192.168.1.3, Subnet mask 255.255.255.0

Procedure

- Connect PC0 to Switch0.
- Connect PC1 to Switch0.
- Use Copper Straight-Through cables to connect switches to server-PT.
- Assign the required IP addresses to all the PCs.
- open Server0 and go to Desktop → IP Configuration. Select the Static option and enter the IP address 192.168.1.3 with the subnet mask 255.255.255.0
- open Server0 and go to Services → FTP. Turn the FTP service ON and create a username and password for accessing the server.




- open PC0 and go to Desktop → Text Editor. Create a text file and save it as file.txt.




- open PC0 → Desktop → Command Prompt and enter ftp 192.168.1.3. When asked, enter the FTP username and password. After successful login, the FTP connection will be established.



- To upload the file to the server, type put file.txt in the FTP command prompt. The file will then be transferred from PC0 to Server0.



- To download the file from the server, type get file.txt. The file will be transferred from Server0 back to the client PC.



Observation

The FTP connection was successfully established between the client PC and Server0. The file was uploaded to the server using the put command and downloaded back to the client using the get command.

Result

FTP was successfully implemented in Cisco Packet Tracer. The client connected to the FTP server using authentication, and the file was successfully uploaded and downloaded.