
HOW TO SECURE GOOGLE CHROME

A practical guide to safer browsing

Muhsin farhan khalif

Updates • Safe Browsing • Passwords • Permissions • Extensions



Includes illustrated Chrome-style screenshots. These are instructional mockups, not live screenshots; your Chrome menus may look slightly different.

Before You Start

Google Chrome includes built-in tools that help protect you from malicious websites, unsafe downloads, weak passwords, and unwanted permissions. The exact wording and placement of settings can vary by Chrome version, operating system, or organization policy.


Quick access: type one of these addresses into Chrome's address bar and press Enter:

- chrome://settings/safetyCheck — Safety Check
- chrome://settings/help — Update Chrome
- chrome://settings/security — Safe Browsing
- chrome://extensions — Manage extensions
- chrome://settings/content — Website permissions
- chrome://settings/clearBrowserData — Clear browsing data

1. Run Chrome Safety Check

Safety Check reviews several important browser protections and tells you when action may be needed.

1. Open Chrome and select the three-dot menu in the top-right corner.
2. Choose Settings, then Privacy and security.
3. Select Safety Check, or enter chrome://settings/safetyCheck in the address bar.
4. Select Check now and wait for the review to finish.
5. Follow the recommendations shown, such as updating Chrome or reviewing unsafe passwords and extensions.




Security tip: Run Safety Check regularly and whenever you suspect a browser problem.

2. Update Google Chrome

Updates often include important security fixes. Use the built-in About Chrome page to check your version.

6. Open Chrome and select the three-dot menu.

7. Go to Help → About Google Chrome, or type chrome://settings/help.
8. Let Chrome check for updates and install any available update.
9. If Chrome asks you to relaunch, save your work in open tabs and select Relaunch.
10. Return to About Chrome later if you need to confirm that the update completed.




Security tip: Download Chrome updates only through Chrome itself or Google's official website.

3. Turn On Safe Browsing

Safe Browsing helps warn you about known dangerous websites, downloads, and extensions.

11. Open Settings → Privacy and security → Security, or enter chrome://settings/security.
12. Find the Safe Browsing section.
13. Choose Enhanced protection for the strongest available proactive protection, if it suits your privacy needs.
14. If you prefer Standard protection, keep it enabled rather than turning protection off.
15. Read Chrome's on-screen explanation so you understand what information each level may send to Google.




Security tip: No protection is not recommended. Protection settings can have privacy trade-offs; review the current Chrome explanation.

4. Check Saved Passwords

A password that has been exposed, reused, or is easy to guess can put multiple accounts at risk.

16. Open the Google Password Manager from Chrome's menu, or visit passwords.google.com.
17. Choose Password Checkup or the available password-checking option.
18. Review any compromised, reused, or weak passwords reported.
19. Change affected passwords on the official websites or apps, starting with email and financial accounts.
20. Use a unique, long password for every account and consider a reputable password manager.


21. 

Security tip: Never share a password or one-time verification code with someone who contacts you unexpectedly.

5. Review Website Permissions

Websites may request access to your camera, microphone, location, notifications, or other device features.

22. Open Settings → Privacy and security → Site settings, or enter chrome://settings/content.
23. Open each permission category, such as Camera, Microphone, Location, and Notifications.
24. Set permissions to Ask before allowing access where possible, or Block permissions that you do not need.
25. Review websites already listed as allowed and remove access for sites you do not trust.
26. When a site requests a permission, allow it only if the feature is necessary and the site is legitimate.


27. 

Security tip: A website should not need camera, microphone, or location access without a clear reason.

6. Remove Untrusted Extensions

Extensions can read or change website data depending on the permissions they receive.

28. Type chrome://extensions into the address bar.
29. Review every installed extension and confirm that you recognize it and still need it.
30. Select Details to inspect the extension’s permissions and publisher information.
31. Turn off or remove extensions you do not recognize, no longer use, or do not trust.
32. Install extensions only from the official Chrome Web Store and check the publisher and reviews carefully.


33. 

Security tip: Be cautious with extensions that promise unrealistic results or request broad access unrelated to their purpose.

7. Clear Browsing Data When Appropriate

Clearing browsing data can help protect privacy on shared devices, but it may sign you out of websites.

34. Open Settings → Privacy and security → Delete browsing data, or enter chrome://settings/clearBrowserData.
35. Choose a time range.
36. Select only the data types you intend to remove, such as browsing history, cookies, or cached files.
37. Read the options carefully, then select Delete data.
38. If you use Chrome Sync or a shared device, understand what is stored locally and what may be synced before deleting.


39. 

Security tip: On a public or shared computer, sign out of accounts and close all browser windows when finished.

8. Check Websites Before You Sign In

A secure connection is useful, but it does not guarantee that a website is honest. Scammers can also use HTTPS.


40. Read the full website address carefully and check for misspellings or extra words in the domain.
41. For important services, type the known address yourself or use a trusted bookmark instead of following unexpected links.
42. Check that the connection uses HTTPS, but do not treat the padlock or HTTPS alone as proof that the site is legitimate.
43. Do not enter passwords, payment details, or personal information on pages opened from suspicious emails, pop-ups, or messages.
44. If Chrome displays a red warning page, do not bypass it unless you fully understand the risk and have verified the site through a trusted route.

45. 

Security tip: When in doubt, close the tab and contact the organization through its official website or phone number.


9. Extra Habits for Better Security

- Keep your operating system and antivirus/security software updated.
- Do not install software or browser extensions from unknown websites.
- Avoid opening unexpected attachments or links, even if the message appears to come from someone you know.
- Use a separate Chrome profile for work and personal browsing if that helps you keep accounts organized.
- Enable two-step verification on important accounts, especially your email account.
- Lock your computer when you leave it unattended and do not save passwords on public computers.
- If you suspect malware, stop entering sensitive information and use trusted security software to scan the device.



Security Checklist

- ✓ Chrome is updated to the latest version available to my device.
- ✓ I ran Safety Check and reviewed its recommendations.
- ✓ Safe Browsing is enabled.
- ✓ I checked saved passwords and changed any compromised ones.
- ✓ Camera, microphone, location, and notification permissions are reviewed.
- ✓ I removed extensions I do not recognize or need.
- ✓ I know how to identify suspicious website addresses and phishing links.
- ✓ My important accounts use unique passwords and two-step verification.



Official Help and References

- **Google Chrome Help — Update Google Chrome:** https://support.google.com/chrome/answer/95414
- **Google Chrome Help — Safety Check:** https://support.google.com/chrome/answer/10468685
- **Google Chrome Help — Choose Safe Browsing protection:** https://support.google.com/chrome/answer/9890866
- **Google Password Manager:** https://passwords.google.com/
- **Chrome Web Store:** https://chromewebstore.google.com/

Note: This guide is for general education. Chrome's interface and available controls may change over time. Follow the instructions displayed in your current browser.