# **Software Performance Engineering - SPE**



Optimized C++

Ed Keenan


6 March 2019

13.0.6.5.6 Mayan Long Count



### Goals

- What is SPE?
- Performance
  - Models
  - Responsiveness
  - Scalability
- Myths
- Strategies
- Modeling
- Distributed Issues









#### Book:


 Performance Solutions: A practical guide to creating responsive, scalable software

#### Articles:

- Five Steps to Solving Software Performance Problems
- Making the Business Case for Software Performance Engineering
- Best Practices for Software Performance Engineering

#### Authors:

Connie Smith and Lloyd Williams







### Software Performance Engineering

- Software performance engineering (SPE)
  - A systematic, quantitative approach to constructing software systems that meet performance objectives.
- SPE prescribes
  - principles for creating responsive software
  - the data required for evaluation
  - procedures for obtaining performance specifications
  - guidelines for conducting performance evaluation at each development stage



### **Model Based**



- SPE is model based
  - Building and analyzing models of the proposed software
  - Explore model's characteristics
    - Determine whether it meets the requirements before we build the system
- Techniques are neither new or revolutionary
  - Evolved from proven quantitative disciplines



### **Performance**



- Performance is the degree to which a software system or component meets its objectives for timelines
- Performance is an indicator of how well a software system meets its requirement on timeliness
  - Response time
  - Throughput time



### Responsiveness




- Responsiveness is the ability of a system to meet its objectives for response time or throughput.
- Responsiveness has both an objective and a subjective component
- Example:
  - improve the perceived responsive of a web application by present the user-writable fields first.





- Scalability is the ability of a system to continue to meet its response time and throughput objectives as the demand for the software functions increases.
- At some point a small increase in load begins to have a great effect on response time.





### **Causes of Performance Loss**



- Problems introduced at beginning of project
  - Attitude:
    - Let's get it done
    - If performance problem fix it later
- Many encourage this attitude
  - Get the structure and flow working
  - We'll focus on optimizing the small part that's problematic
    - We'll be more efficient



# **Performance Myth**



### Myth 1:

- Based on the assumption that you need something to measure before you can begin to manage performance
  - It is not possible to do anything about performance until you have something executing to measure

### Reality

- You don't need to wait
- Use performance models at the early architectural and early design phases
- Models allow you estimate the performance and predict the final performance



# **Performance Myth**



### Myth 2:

- Based on the fear that adding performance management to the software process will delay project completion
  - Managing performance takes too much time

### Reality

- Do not automatically require addition time
- Amount of effort is required is proportional to the level of performance risk your system
- Fixing and identifying problems at the early stage saves time in the end



# **Performance Myth**



- Myth 3:
  - Based on the fear that adding performance modeling will take too much time and consume too many project resources
    - Performance models are complex and expensive to construct
- Reality
  - Simple models work extremely well
  - Simple models are inexpensive to construct and evaluate



# **Getting it Right**



- Even if you Rely on hardware to solve performance problems
  - Use performance models early
    - Before other options are closed
  - Verify that this a cost-effective solution
    - IBM server example
- Sometimes End to End performance testing is not possible
  - Performance models are the only option



# Proactive performance



- The use of new software technology requires careful attention to performance until the performance aspects of the new technology are understood
- Intuition about performance problems is not sufficient
  - Quantitative assessments are necessary to assess performance risks
- Performance engineering reactively on systems that use unfamiliar technology
  - Probability of performance failure is much higher



### SPE




- Answers the following questions:
  - Will your users be able to complete tasks in the allotted time?
  - Are your hardware and network capable of supporting the load?
  - What response time is expected for key tasks?
  - Will the system scale up to meet your future needs?



### **Performance Balance**

- Detect problems early
- Quantitative Assessment
  - Begins early, frequency matches system criticality
- Often find architecture and design alternatives with lower resource requirements
- Select cost-effective performance solutions early



Resource Requirements



# **SPE Modeling Strategies**




- Simple-Model Strategy
  - Simplest possible model that identifies problems with the system architecture, design or implementation plans
- Best- and Worst-Case Strategy
  - Best- and worst-case estimates of resource requirements to establish bounds on expected performance and manage uncertainty in estimates
- Adapt-to-Precision Strategy
  - Match the details represented in the models to your knowledge of the software processing details




### **SPE Model-based Approach**



#### Conventional Models



#### Software Prediction Models









- Low overhead
  - use the simplest possible model that identifies problems
- Accommodate:
  - incomplete definitions
  - imprecise performance specifications
  - changes and evolution
- Goals:
  - initially distinguish between "good" and "bad"
    - later, increase precision of predictions
  - provide decision support



# **SPE Process Steps**



- Assess performance risk
  - Identify critical use cases
- 2. Select key performance scenarios
  - Establish performance objectives
- 3. Construct performance models
  - Determine software resource requirements
- 4. Evaluate the models
  - Verify and validate the models



### **Workload Data**



- Pareto principle (80-20 rule)
  - Typically 80% of the software execution will run in 20% of the code
- First: scenarios of typical activity
  - Number of concurrent users
  - Request arrival rates
  - Performance goals
- Later:
  - add large scenarios, critical scenarios, etc.



# **Software Specifications**



- Execution paths for scenarios of interest
- Objects / methods to be executed
  - probability of execution
  - number of repetitions
  - protocol
- Slow Dependencies
  - Networking
  - Database accesses
- Level of detail increases as development progresses



# **Understand Resource Usage**




- CPU
  - Work Units
  - Number of instructions executed or measurements of similar software
- I/O
  - External devices
- Communication
  - Networking
  - Database calls







- Types of solutions:
  - Best case shortest path in graph
  - Worst case longest path in graph
  - Average
  - Variance
- Approach
  - Repeat reduction rules on typical structures until graph contains one node with the computed solution
  - Apply reductions to each resource specification (t), then combine the results







### **Simple Reduction Rules:**

# **Average Analysis**






$$t = t_1 + t_2 + ... + t_n$$



$$t = nt_1$$

**Loop Structures** 



$$t = t_0 + p_1 t_1 + p_2 t_2$$

Case Nodes

**Sequential Structures** 



# System Execution Model



- Characterizes performance in the presence of factors that could cause contention for resources
  - Multiple workloads
  - Multiple users



# System Execution Model




- Provides additional information
  - Metrics that account for resource contention
  - Sensitivity of performance metrics
    - to variations in workload composition
  - Scalability of the hardware and software
    - Identification of bottleneck resources
  - Comparative data on options:
    - workload changes, software changes, hardware upgrades, and various combinations of each



#### **ATM** – example:

# **System Performance Model**











- What is the System Performance model?
  - You are making a simulator
    - Simulate the load with the models
    - Can be as accurate or inaccurate as you desire
    - Look for trends



# **Distributed Modeling?**




- Simple-Model strategy
  - Start with software execution model
  - One scenario/processor at a time
- Approximate delays
  - Communication/ synchronization
- If software execution model shows no problems, proceed to
  - System execution model
  - Advanced system execution model



# Partitioning the Model






Estimate the Delay for System Interactions




### **Message Types**







**Synchronous** 



**Deferred Synchronous** 



Asynchronous




Asynchronous Callback




# **Synchronization Nodes**




#### Calling Process:



Synchronous call; the caller waits for a reply




Deferred synchronous call; processing occurs, wait for reply




Asynchronous call; no reply

#### Called Process:



Reply



No reply



### Summary



- Early modeling is important for performance related design
- Distributed systems
  - Use Simple-Model strategy
- With SPE you can gain insights into:
  - Performance principles
  - Patterns
  - Anti-patterns
  - That affect your design



### **Thank You!**





Questions?

### **Profiler**



Optimized C++


Ed Keenan



### Goals



- Basics
  - Profiling
  - Hot Spot
  - Instrumenting
  - Bottlenecks
- VTune Example
  - Sampling
  - Call Graph
  - Event Based
- Popular Profilers
  - Intel
  - Microsoft
  - Apple





## **Review Material**



- General References from Web
- Basics of VTune<sup>™</sup> Performance Analyzer
  - Intel Software College
- Profiling tools
  - By Vitaly Kroivets
- Great Lecture on internals
  - Software Performance Profiling
    - MAE Presentation Nagy Mostafa







## **Efficient Code?**



- Efficiency
  - Describe properties of an algorithm relating to how much of various types of resources it consumes
- Algorithmic efficiency
  - Thought of as analogous to engineering productivity for a repeating or continuous process.
  - Goal is to reduce resource consumption
    - Time to completion to some optimal level



# **Profiling**



- Software profiling
  - Form of dynamic program analysis that measures:
    - usage of memory, usage of particular instructions, or frequency and duration of function calls
    - Common use of profiling information is to aid program optimization
  - Profiling is achieved by instrumenting either the program source code or its binary executable form using a tool called a profiler
- Methodology of the profiler
  - Event-based
  - Statistical
  - Instrumentation
  - Simulation







- Profilers use a wide variety of techniques to collect data
  - hardware interrupts
  - code instrumentation
  - instruction set simulation
  - operating system hooks
  - performance counters



# **Hot Spot Analysis**



- To diagnose hot spots
  - During actual execution of computer programs
  - Use real or test data
  - Performance analysis under generally repeatable conditions
- Identify pinpoint sections of the code
  - Specifically targeted programmer optimization without necessarily spending time optimizing the rest of the code
- Re-Running the program
  - Measure of relative improvement can then be determined
  - Determine if the optimization was successful



## Amdahl's Law




- Amdahl's law also known as Amdahl's argument
  - Named after computer architect Gene Amdahl
  - Finds the maximum expected improvement to an overall system when only part of the system is improved
  - Is often used in parallel computing to predict the theoretical maximum speedup using multiple processors
- Speedup of a program using multiple processors in parallel computing is limited by the time needed for the sequential fraction of the program
  - Applies to any optimization, single CPU or parallel CPUs







- if a program needs 20 hours with a single processor
  - a particular portion of 1 hour cannot be parallelized
  - while the remaining promising portion of 19 hours (95%) can be parallelized
  - How we parallelized execution of this program
  - -> minimum execution time cannot be less than that critical 1 hour
    - Hence the speedup is limited up to 20x





## **Profiles & Traces confusion**



#### Profile

- A statistical summary of the events observed
- Summary profile information is often annotated against the source code statements where the events occur,
- Size of measurement data is linear to the code size of the program

#### Trace

- A stream of recorded events
- Performance problems in parallel programs (waiting for messages or synchronization issues) often depend on the time relationship of events
  - Requiring a full trace to get an understanding of what is happening.







- Sampling Profilers
  - Statistical Profilers
    - Time Based
  - Event Based Profilers
- Instrumenting profilers



# Statistical profilers



- A sampling profiler probes the target program's program counter at regular intervals using operating system interrupts
  - Sampling profiles are typically less numerically accurate and specific
  - Allow the target program to run at near full speed
  - Resulting data are not exact, but a statistical approximation
    - Can often provide a more accurate view
- Not as intrusive to the target program
  - Don't have as many side effects
    - Don't affect the execution speed as much, they can detect issues that would otherwise be hidden.
- Some processors have JTAG interface which samples the program counter in a truly undetectable manner.



# Instrumenting profilers



- Some profilers instrument the target program with additional instructions to collect the required information.
- Instrumenting the program can cause changes in the performance of the program
  - Potentially causing inaccurate results and heisenbugs
    - A heisenbug (named after the Heisenberg uncertainty principle) is a computer bug that disappears or alters its characteristics when an attempt is made to study it.
- Instrumenting will always have some impact on the program execution, typically always slowing it.
  - Instrumentation can be carefully controlled to have a minimal impact.
  - Impact on a particular program depends on the placement of instrumentation points and the mechanism used to capture the trace
  - Our class Timer is an instrument
- New hardware support for trace capture means that on some targets, instrumentation can be on just one machine instruction.



# Performance analysis



- Performance analysis
  - Commonly known as profiling
  - Is the investigation of a program's behavior using information gathered as the program executes.
  - Its goal is to determine which sections of a program to optimize.
- A profiler is a performance analysis tool
  - Measures the behavior of a program as it executes
    - Particularly the frequency and duration of function calls.
- Performance analysis tools existed at least from the early 1970s.
  - Profilers may be classified according to their output types, or their methods for data gathering.



# **Self-tuning**



- A self-tuning system is capable of optimizing its own internal running parameters in order to maximize or minimize the fulfillment of an objective function typically the maximization of efficiency or error minimization.
  - Self-tuning systems typically exhibit non-linear adaptive control.
  - Self-tuning systems have been a hallmark of the aerospace industry for decades, as this sort of feedback is necessary to generate optimal multi-variable control for nonlinear processes.
- Game development is now moving to self-tuning schemes.



### **Bottlenecks**



- Bottleneck is the part of a system which is at capacity.
  - Other parts of the system will be idle, waiting for it to perform its task.
- The process of finding and removing bottlenecks
  - Need to prove their existence
    - By sampling, before acting to remove them.
  - Avoid a strong temptation to guess.
    - Guesses are often wrong, and investing only in guesses can itself be a bottleneck



# Performance Tuning



- Performance tuning is the improvement of system performance
  - Most systems will respond to increased load with some degree of decreasing performance.
  - A system's ability to accept higher load is called scalability
  - Modifying a system to handle a higher load is synonymous to performance tuning.
- Problems may be identified by slow or unresponsive systems.
  - Due to high system loading, causing some part of the system to reach a limit in its ability to respond.



#### **Performance Tuning:**

## **Steps**



- Generalized steps
  - Assess problem, establish metrics that categorize acceptable behavior.
  - Measure the performance of the system before modification.
  - Identify the bottleneck, is critical for improving the performance.
  - Modify/Refactor that part of the system to remove the bottleneck.
  - Measure the performance of the system after modification.



## **Profiler Ouputs**



### Flat profiler

 Flat profilers compute the average call times, from the calls, and do not break down the call times based on the callee or the context.

## Call-graph profiler

 Call graph profilers show the call times, and frequencies of the functions, and also the callchains involved based on the callee. However context is not preserved.



## **Profilers**



- Helps you identify and characterize performance issues by:
  - Collecting performance data from the system running your application.
  - Organizing and displaying the data in a variety of interactive views, from system-wide down to source code or processor instruction perspective.
  - Identifying potential performance issues and suggesting improvements.




# **VTune: Example**




# **Sampling Data**






## Call Graphs





# Sampling over Time









# VTune Source View





### **Counter Monitor**







## **Hot Spots**



 Where in an application or system there is a significant amount of activity

#### Where

 address in memory => OS process => OS thread => executable file or module => user function (requires symbols) => line of source code (requires symbols with line numbers) or processor (assembly) instruction

#### Significant

 activity that occurs infrequently probably does not have much impact on system performance

#### Activity

- time spent or other internal processor event
- Examples of other events: Cache misses, branch mispredictions, floating-point instructions retired, partial register stalls, and so on.



# VTune Sampling Collector



- Periodically interrupt the processor to obtain the execution context
  - Time-based sampling (TBS) is triggered by:
    - Operating system timer services
    - Every n processor clockticks
  - Event-based sampling (EBS) is triggered by processor event counter overflow
    - These events are processor-specific, like L2 cache misses, branch mispredictions, floating-point instructions retired, and so on



## **Benefits to Sampling**



- You do not have to modify your code.
  - But DO compile/link with symbols and line numbers.
  - But DO make release builds with optimizations.
- Sampling is system-wide.
  - Not just YOUR application.
  - You can see activity in operating system code, including drivers.
- Sampling overhead is very low.
  - Validity is highest when perturbation is low.
  - Overhead can be reduced further by turning off progress meters in the user interface.



# VTune What Can You Profile?




- Win32 applications
- Stand-alone Win32\* DLLs
- Stand-alone COM+ DLLs
- Java applications
- .NET\* applications
- ASP.NET applications
- Linux32\* applications



# VTune **Tuning Assistant**





Provides
Tuning
Advice
Based on
Performance
Data







- Intel® VTune<sup>™</sup> Amplifier XE is a software performance analysis for 32 and 64-bit x86 based machines, and has both GUI and command line interfaces.
  - OS: Linux and Microsoft Windows
- Intel VTune Amplifier XE assists in various profiling
  - including stack sampling,
  - thread profiling
  - hardware event sampling.
- Profiler result consists of details:
  - time spent in each sub routine which can be drilled down to the instruction level
  - time taken by the instructions are indicative of any stalls in the pipeline during instruction execution
  - tool can be also used to analyze thread performance.



# Microsoft Visual Studio Team System Profiler



- Visual Studio Team System Profiler by Microsoft
  - Integrated into the Visual Studio Team System (VSTS) suite and the Development Edition of Visual Studio
- Works in either in sampling or instrumentation mode.
  - VSTS profiler helps to resolve performance problems in code written for the .NET platform or Visual C++ code
- Profiler the application will need to be launched and the component (screen) to be analyzed needs to be executed normally and exited
  - After completing, the profiler gives a summary of the elapsed time for each of the functions and the number of time each function is called. Also the memory usage data of the objects can also be tracked.



## **Apple: Instruments**



- Instruments (formerly Xray)
  - Performance analyzer and visualizer, integrated in Xcode 3.0 and later
  - Instruments shows a time line displaying any event occurring in the application
  - CPU activity variation, memory allocation, and network and file activity, together with graphs and statistics.
- Group of events are monitored via customizable "instruments"
  - Which record user generated events and replay (emulate) them exactly as many times as needed
  - Developer can see the effect of code changes without actually doing the repetitive work.
  - Instrument Builder feature allows the creation of custom analysis instruments.
- Built-in instruments can track
  - User events, such as keyboard keys pressed and mouse moves and clicks with exact time.
  - CPU activity of processes and threads.
  - Memory allocation and release, garbage collection and memory leaks.
  - File reads, writes, locks.
  - Network activity and traffic.
  - Graphics and inner workings of OpenGL.



# You can get these tools



- Apple Instruments
  - Free part of Xcode
- VSTS profiler
  - MSDNAA DePaul for students
  - Ultimate Edition
- Intel VTune Profiler
  - Get a trial version today!



#### **Thank You!**





Questions?





Optimized C++

Ed Keenan



#### Goals



- Strings
  - Historical
    - PIA Background






#### References:



- Internet articles,
  - "The Absolute Minimum Every Software Developer Absolutely, Positively Must Know About Unicode and Character Sets (No Excuses!)"
  - "Back to Basics"
    - by Joel Spolsky
      - http://www.joelonsoftware.com/
  - This Guy is Great!
- He has a great book
  - "Joel on Software: And on Diverse and Occasionally Related Matters That Will Prove of Interest to Software Developers, Designers, and Managers, and to Those Who, Whether by Good Fortune or III Luck, Work with Them in Some Capacity "
    - Please buy a copy endless enjoyment





# Before we talk optimization



- We should define what a string is?
  - I thought this was a simple task
    - 1-2 slides tops
  - But hang-on
    - Bring a bag lunch
    - It's a doozy
  - I learned a lot in this exploration
    - Hopefully you will.



# History 1950-1960s



#### EBCDIC

- Extended Binary Coded Decimal Interchange Code (EBCDIC) is an 8-bit character encoding used mainly on IBM mainframe and IBM midrange computer operating systems.
- EBCDIC descended from the code used with punched cards and the corresponding six bit binary-coded decimal code used with most of IBM's computer peripherals of the late 1950s and early 1960s

#### BCD

What is that?



#### **History 1950-1960s**

- EBCDIC alphabetic characters follow a punched card encoding convention rather than a linear ordering like ASCII.
  - One consequence of this is that incrementing the character code for "I" does not produce the code for "J"
- Question:
  - The American government went to IBM to come up with an encryption standard, and they came up with...
- Answer:
  - EBCDIC!

2nd hex digit EBCDIC character codes 1st hex digit									_							
0 1 2 3 4 5 6										9	Α	В	С	D	Е	F
0	NUL	DLE	DS		SP	&	-									0
1	SOH	DCI	sos				7		а	j			Α	J		1
2	STX	DC2	FS	SYN					Ь	k	s		В	К	S	2
3	ETX	TM							C	-	t		С	L	Т	3
4	PF	RES	BYP	PN					d	m	u		D	М	U	4
5	HT	NL	LF	RS					е	п	v		Е	N	٧	5
6	LC	BS	ETB	UC					f	0	w		F	0	W	6
7	DEL	IL	ESC	EOT					g	р	х		G	Р	Х	7
8		CAN							h	q	у		Н	Q	Υ	8
9		EM							i	r	z	,	ı	R	Z	9
Α	SMM	CC	SM		C CENT	i		;								
В	VT	CUI	CU2	CU3		\$	1	#								
С	FF	IFS		DC4	<	*	%	@								
D	CR	IGS	ENQ	NAK	(	)	_	'								
Е	so	IRS	ACK		+	;	>	=								
F	SI	IUS	BEL	SUB	- 1		?	*								



# Simple character set



#### ASCII

- Only characters that mattered were good old unaccented English letters
- A code for them called ASCII which was able to represent every character using a number between 32 and 127
- Everything be stored in 7 bits
  - Decimal (0 127)
  - Hex (0 0x3F)

#### Example:

- <space> was 32d
- Letter "A' was 65d
- Letter "B" was 66d, etc.







Dec	H)	Oct	Char		Dec	Нх	Oct	Html	Chr	Dec	Нх	Oct	Html	Chr	Dec	Нх	Oct	Html Ch	<u>ır</u>
0	0	000	NUL	(null)	32	20	040	a#32;	Space	64	40	100	a#64;	0	96	60	140	& <b>#</b> 96;	8
1	1	001	SOH	(start of heading)	33	21	041	@#33;	!	65	41	101	a#65;	A	97	61	141	@#97;	a
2	2	002	STX	(start of text)	34	22	042	@#3 <b>4</b> ;	rr	66	42	102	<b>B</b> ;	В	98	62	142	<b>b</b>	b
3	3	003	ETX	(end of text)	35	23	043	<b>#</b> ;	#	67	43	103	a#67;	С				& <b>#</b> 99;	
4	4	004	EOT	(end of transmission)	36	24	044	<b>\$</b>	ş	68	44	104	<b>D</b>	D	100	64	144	d	d
5				(enquiry)				<b>%</b>					<b>E</b>					e	
6				(acknowledge)				<b>&amp;</b>					a#70;					f	
7	- 7	007	BEL	(bell)	39	27	047	<b>'</b>	1				G			-		g	
8	_	010		(backspace)				a#40;					H					<b>4</b> ;	
9				(horizontal tab)				)					a#73;					i	
10		012		(NL line feed, new line)				6#42;					a#74;					j	
11		013		(vertical tab)				a#43;					a#75;					k	
12		014		(NP form feed, new page)				a#44;					a#76;					l	
13	_	015		(carriage return)				a#45;					<u>@#77;</u>					m	
14		016		(shift out)				a#46;			_		a#78;					n	
15	_	017		(shift in)				6#47;		ı ·-			a#79;					o	
				(data link escape)				a#48;					<b>P</b>					p	
								a#49;					Q	_				q	_
				(device control 2)				a#50;					6#82;		ı — —  -	. –		r	
				(device control 3)				3					<b>S</b>		I — — -			s	
				(device control 4)				<u>6</u> #52;					a#84;		I — — -			t	
				(negative acknowledge)				a#53;					<b>U</b>		1			u	
22	16	026	SYN	(synchronous idle)				a#54;					<b>V</b>		I — — -			v	
				(end of trans. block)				<b>7</b> ;		I			W					w	
				(cancel)				<b>8</b>					<b>X</b> ;					x	
25	19	031	EM	(end of medium)				a#57;					<b>Y</b>		I — — —			y	_
26	lA	032	SUB	(substitute)				<b>:</b>		I			Z					z	
27	1B	033	ESC	(escape)				<b>;</b>		I			[	-	I — — -			{	
		034		(file separator)				4#60;					\					<b>4</b> ;	
29	1D	035	GS	(group separator)				=		I			& <b>#</b> 93;	-	ı			}	
		036		(record separator)				>		I			a#94;					~	
31	1F	037	US	(unit separator)	63	ЗF	077	<b>?</b>	2	95	5F	137	a#95;	_	127	7F	177		DEL



# **Opportunity?**



- Most computers in those days were using 8bit bytes
  - So <u>not only</u> could you store every possible ASCII character
  - Had a whole bit to spare.
  - 128 extra entries
- What do we do with all that extra space?



## **Parity**



#### Aside:

- Early days data was encoded in 7 bits, the most significant bit was the parity bit
- Used for error encoding
- Hardware level assignment / check

#### Result

- 0 if sum of bits 0:7 is even
- 1 if sum of bits 0:1 is odd



## **Parity differences**



#### Size:

- 2 MB 3.5 DD DS floppy
  - Double density, double sided
  - IBM: 40 tracks, 9 sectors, 512 bytes per sector
- Formatted for IBM:
  - 40 \* 9 \* 512 \* 8 bits = 1474560 bits
  - 1474560 bits / (1024 \* 1024) = 1.406 MB
- Formatted for Mac
  - 40 \* 9 \* 512 \* 8 \* (64/56) parity ratio = 1685211 bits
  - 1685211 bits / (1024 \* 1024) = 1.607 MB



#### **ASCII**



- Unprintable code
  - Codes below 32 were called unprintable
  - Used for control characters
    - 7 which made your computer beep
    - 12 which caused the current page of paper to go flying out of the printer and a new one to be fed in



# Using the extended range



- Use codes 128-255 for our own purposes?
  - Many people had their own ideas
  - IBM-PC
    - OEM character set which provided some accented characters for European languages
    - Added a bunch of line drawing characters
      - horizontal bars, vertical bars, horizontal bars with little dingle-dangles dangling off the right side, etc.,
      - Use these line drawing characters to make spiffy boxes and lines on the screen
      - Can still see on the 8088 computer at your dry cleaners







```
128
      Ç
            144
                   É
                                                                                           240
                                                                       Ш
                          160
                                                           L
                                                                208
                                                                              224
                                       176
                                                    192
129
            145
                                                                              225
                                                                                           241
                                                                                     ß
                                       177
                                                    193
                                                                209
                          161
             146
                                                                              226
                                                                                           242
130
                                                     194
                                                                210
                          162
                                       178
131
             147
                                                                                           243
                                                     195
                                                                 211
                                                                              227
                          163
                                       179
                                                                                           244
132
             148
                                                                               228
                                                                                     Σ
                          164
                                ñ
                                       180
                                                     196
                                                                 212
133
             149
                                Ñ
                                                                               229
                                                                                           245
                          165
                                                     197
                                                                213
                                       181
134
             150
                                                     198
                                                                214
                                                                              230
                                                                                           246
                          166
                                       182
135
             151
                                                                               231
                                                                                           247
                                                     199
                                                                215
                          167
                                       183
136
             152
                                                     200
                                                                216
                                                                              232
                                                                                     Φ
                                                                                           248
                          168
                                       184
137
             153
                                                                              233
                                                                                           249
                          169
                                       185
                                                     201
                                                                 217
138
             154
                                                                                           250
                                                     202
                                                                 218
                                                                              234
                          170
                                       186
                                                                                           251
139
             155.
                                                     203
                                                                 219
                                                                               235
                          171
                                1/2
                                       187
140
                                                                                           252
             156
                                                     204
                                                                 220
                                                                              236
                          172
                                       188
141
            157
                                                     205
                                                                               237
                                                                                           253
                          173
                                       189
                                                                 221
     Ä
142
            158
                          174
                                                     206
                                                                 222
                                                                               238
                                                                                           254
                                       190
143
                                                                                           255
             159
                                                     207
                                                                 223
                                                                               239
                          175
                                       191
```

Source: www.LookupTables.com



## Wild west extended range



- Outside of America all kinds of different OEM character sets were created
  - All used the top 128 characters for their own purposes
  - Example:
    - character code 130 would display as é in the USA
    - Hebrew letter Gimel (x) in Israel
      - Americans would send their résumés to Israel they would arrive as rasumas
    - In Russian, there were lots of different ideas of what to do with the upper-128 characters, so you couldn't even reliably interchange Russian documents.



#### **ANSI** standard



- OEM free-for-all got codified in the ANSI standard
  - Codes < 128</li>
    - Which was pretty much the same as ASCII
  - Codes >= 128 many different ways to handle characters
    - Different systems depending on its <u>Code Page</u>
      - Israel code page is 862
      - Greece code page is 737
    - If they are below 128 uses the same character mapping
    - If greater than 128, characters are mapped based on its Code Page
- National versions of MS-DOS had dozens of these code pages
  - Everything from English to Icelandic
  - a few "multilingual" code pages that could do Esperanto and Galician on the same computer.







- Code pages
  - http://www.i18nguy.
     com/unicode/codep
     ages.html#msftdos
  - Many different pages
    - Take a look

Microsoft's Windows code pages  Microsoft's Windows code pages  by country
Windows CP 1250 (Central Europe)
Windows CP 1251 (Cyrillic)
Windows CP 1252 (Latin I)
Windows CP 1253 (Greek)
Windows CP 1254 (Turkish)
Windows CP 1255 (Hebrew)
Windows CP 1256 (Arabic)
Windows CP 1257 (Baltic)
Windows CP 1258 (Viet Nam)
Windows CP 874 (Thai)



# **Code Pages**



Unicode Charts
Unicode Charts
Unicode character name index
UTF-32 (TR-19)
Character Encoding Model (TR-17)
Basic Latin
Latin-1 Supplement
Latin Extended-A
Combining Diacritical Marks
Greek
Cyrillic
Hebrew
I18n Guy's Hebrew Unicode Chart
Arabic
Currency Symbols
Hangul Jamo
Hiragana
I18n Guy's Hiragana Unicode Chart
Katakana

IBM Asian Code pages
I18n Guy's Hiragana Unicode Chart
CP 00290 (EBCDIC) Japanese (Katakana) Non-extended
CP 00290 (EBCDIC) Japanese (Katakana) Extended
CP 00833 (EBCDIC) Korea Extended
CP 00836 (EBCDIC) Simplified Chinese Extended
CP 00891 (IBM PC) Korea
CP 00895 Japan 7-Bit
CP 00897 (IBM PC) Japan PC #1
CP 00903 (IBM PC) People's Republic of China (PRC)
CP 00904 (IBM PC) Republic of China (ROC)
CP 00905 (EBCDIC) Turkey Extended CP
CP 01027 (EBCDIC) Japanese (Latin) Extended
CP 01040 (IBM PC) Korean Extended
CP 01041 (IBM PC) Japanese Extended
CP 01042 (IBM PC) Simplified Chinese Extended
CP 01043 (IBM PC) Traditional Chinese
CP 01088 (IBM PC) Korean
CP 01114 Traditional Chinese (Big5)
CP 01115 Simplified Chinese (GB)



## Asia problem with ANSI



- Asia
  - Even more crazy things
  - Asian alphabets have thousands of letters
    - Never going to fit into 8 bits.
- DBCS double byte character set
  - Solved this messy system.
  - Some letters were stored in one byte and others took two.







- It was easy to move forward in a string
  - Very hard to move backwards due to the encoding.
- Programmers were encouraged NOT to use s++ and s-- to move forwards and backwards
  - Use Windows' AnsiNext and AnsiPrev which knew how to deal with the whole mess



#### But wait there's more...



- Programmers just pretended that a byte was a character
  - A character was 8 bits
  - You never
    - moved a string from one computer to another
    - spoke more than one language
  - Magically all worked
- Internet became common place
  - To move strings from one computer to another
  - Whole mess came tumbling down



# **Introducing Unicode**



- Unicode was a brave effort to create a single character set
  - Included every reasonable writing system
    - Including Klingon and Elvish
- Some people are under the misconception that Unicode is simply a 16-bit code
  - Each character takes 16 bits and therefore there are 65,536 possible characters
  - → This is not, actually, correct
    - It is the single most common myth about Unicode
      - Don't feel bad.



#### **Unicode** – letter definition



- Unicode has a different way of thinking about characters
  - you have to understand the Unicode way of thinking of things or nothing will make sense.
- We've assumed that a letter maps to some bits which you can store on disk or in memory:
  - A -> 0100 0001
- In Unicode
  - A letter maps to a code point which is still just a theoretical concept.
- In Unicode,
  - the letter A is an atomic individual unit
    - A
  - this letter A
    - Is different than B
    - Is different than a
    - Same as A and A and A.
  - The idea that A in a Times New Roman font is the same character as the A in a Helvetica font, but different from "a" in lower case



## Unicode – code point



- Every platonic letter in every alphabet is assigned a magic number by the Unicode consortium which is written like this: U+0639.
  - This magic number is called a code point.
  - The U+ means "Unicode" and the numbers are hexadecimal.
  - Example:
    - U+0639 is the Arabic letter Ain.
    - The English letter A would be U+0041.
  - Unicode website
    - http://www.unicode.org/
- No limit on the number of letters that Unicode can define
  - Gone beyond 65,536 so not every unicode letter can really be squeezed into 2 bytes
  - In fact some unicode is 6 bytes long



## **Unicode - Example**



- String = "Hello"
  - in Unicode, corresponds to these five code points:
    - U+0048 U+0065 U+006C U+006C U+006F.
- Just a bunch of code points.
  - Numbers, really.
  - Now how is it stored in memory?



### **Unicode - Encodings**



- The earliest idea for Unicode encoding
  - Led to the myth about the two bytes
    - Just store those numbers in two bytes each.
  - So "Hello" becomes
    - 00 48 00 65 00 6C 00 6C 00 6F
  - Couldn't it also be?:
    - 48 00 65 00 6C 00 6C 00 6F 00
- Early implementors wanted to be able to store their Unicode code points in big-endian or littleendian mode
  - Whichever their particular CPU was fastest at
  - Unicode was stored in two ways



## **Unicode – Byte Order Marks**



- Programmers were forced to come up with the bizarre convention of storing a 0xFEFF at the beginning of every Unicode string
  - Called a Unicode Byte Order Mark
  - If you are swapping your high and low bytes it will look like a 0xFFFE
  - Programmer reading your string will know that they have to swap every other byte
- Heisenberg effect?
  - How do you know if you are reading a Little-Endian from a Big-Endian?



#### Unicode – All those 0s



- For a while it seemed like that might be good enough, but programmers were complaining.
  - "Look at all those zeros!"
  - Americans looking at English text which rarely used code points above U+00FF.
  - People wanted to conserve bytes
  - Most people decided to ignore Unicode for several years and in the meantime things got worse.



#### UTF-8



- UTF-8 was another system of Unicode code points
  - magic U+ numbers
  - memory using 8 bit bytes
  - http://www.utf-8.com
- In UTF-8
  - Every code point from 0-127 is stored in a single byte.
  - Only code points 128 and above are stored using 2, 3, in fact, up to 6 bytes.

- Side effect that English text looks exactly the same in UTF-8 as it did in ASCII, so Americans don't even notice anything wrong.
  - Only the rest of the world has to jump through hoops. (Go USA!)



#### UTF-8



- "Hello" which was
  - U+0048 U+0065 U+006C U+006C U+006F
- UTF-8
  - stored as 48 65 6C 6C 6F
  - same as ASCII, and ANSI, and every OEM character set on the planet
- UTF-8 is ignorant old string-processing code that wants to use a single 0 byte as the nullterminator will not truncate strings



#### Choices so far



- Unicode 3 ways of storing
  - 2 byte:
    - UCS-2 (unicode 2 bytes)
      - Big Endian
      - Little Endian
    - UTF-16 16 bit (2 byte)
  - UTF 8



# Many other Unicode types



- UTF-7
  - Like UTF-8 but guarantees that the high bit will always be zero
  - Compatible to the old email system that thinks 7 bits are enough
- UCS-4,
  - Stores each code point in 4 bytes
  - Uniform size of each code point
    - A lot of wasted 0 for ASCII type of letters







- Processing a string in the wrong encoding
  - Yields ? in the string
  - 100s of types of encoding
- Single Most Important Fact About Encodings
  - Please remember one extremely important fact:
    - It does not make sense to have a string without knowing what encoding it uses
  - You can no longer stick your head in the sand and pretend that "plain" text is ASCII



# **Encoding declaration**



- How do we preserve this information about what encoding a string uses?
  - For an email message
    - Expected to have a string in the header
      - Content-Type: text/plain; charset="UTF-8"
  - Similar idea for web pages







- Problems with web pages/applications not encoding declaration
  - Gluing many web pages together
  - Many authors using front page generation
- Several internet browsers Guess
  - They look at the code points
  - Try to figure out a pattern
  - Determine a best guess to the encoding
    - Say Bulgaria or Korean



## Windows wchar\_t



- In C++ code we just declare strings as wchar\_t ("wide char") instead of char
- Use the wcs functions instead of the str functions
  - Example:
    - wcscat and wcslen instead of strcat and strlen
- To create a literal UCS-2 string in C code you just put an L before it as so: L"Hello"



### OK – GOT it?



- We now understand
  - Formats
  - Types of strings



## Way Strings work



- C Strings consist of a bunch of bytes followed by a null character, which has the value 0.
  - Implications:
    - There is no way to know where the string ends.
      - Need to moving through the string, looking for the null character at the end.
    - Your string can't have any zeros in it.
      - So an arbitrary binary blob like a JPEG picture CANNOT be in a C string.
- Why do C strings work this way?
  - Because the PDP-7 microprocessor
  - UNIX and the C programming language were invented
    - ASCIZ string meant "ASCII with a Z (zero) at the end."



#### **Strcat**



- Code for strcat
  - Function which appends one string to another.

```
void strcat( char* dest, char* src )
{
     while (*dest) dest++;
     while (*dest++ = *src++);
}
```

- we're walking through the first string looking for its null-terminator
- when we find it
  - we walk through the second string
  - Copying one character at a time onto the first string







Append several strings together

```
char bigString[1000]; /* I never know how much to allocate...
bigString[0] = "\0";
strcat( bigString, "John, ");
strcat( bigString, "Paul, ");
strcat( bigString, "George, ");
strcat( bigString, "Joel ");
```







- 1st Day
  - Shlemiel gets a job as a street painter, painting the dotted lines down the middle of the road.
  - On the first day he takes a can of paint out to the road and finishes 300 yards of the road.
  - "That's pretty good!" says his boss, "you're a fast worker!" and pays him a kopeck.
- 2<sup>nd</sup> Day
  - The next day Shlemiel only gets 150 yards done.
  - "Well, that's not nearly as good as yesterday, but you're still a fast worker. 150 yards is respectable," and pays him a kopeck.
- 3<sup>rd</sup> Day
  - The next day Shlemiel paints 30 yards of the road. "Only 30!" shouts his boss.
  - "That's unacceptable! On the first day you did ten times that much work! What's going on?"
- Shlemiel
  - "I can't help it," says Shlemiel.
  - "Every day I get farther and farther away from the paint can!"



#### Strcat - Shlemiel



- Joke illustrates strcat
  - Scan through the destination string every time
    - Looking for the null terminator again and again.
  - This function is much slower than it needs to be and doesn't scale well at all.
- Lots of code contain this problem.
  - Many file systems are implemented in a way that it's a bad idea to put too many files in one directory
  - Performance starts to drop off dramatically when you get thousands of items in one directory



# Find the Painter's Algo.



- There must be a Shlemiel the Painter's Algorithm in there somewhere.
- Whenever something seems like it should have linear performance but it seems to have nsquared performance
  - Look for hidden Shlemiels.
  - Often hidden by your libraries
  - Looking at a column of strcats or a strcat in a loop doesn't exactly shout out "n-squared," but that is what's happening.



#### **Custom strcat**



```
char* mystrcat( char* dest, char* src )
     {
            while (*dest) dest++;
            while (*dest++ = *src++);
            return --dest;
        }
```

- What have we done here?
  - At very little extra cost we're returning a pointer to the end of the new, longer string.
  - That way the code that calls this function can decide to append further without rescanning the string:







```
char bigString[1000];  /* I never know how much to allocate... */
char *p = bigString;
bigString[0] = '\0';
p = mystrcat (p, "John, ");
p = mystrcat( p, "Paul, ");
p = mystrcat( p, "George, ");
p = mystrcat( p, "Joel ");
```

- Linear in performance
  - Not n-squared
  - Doesn't suffer from degradation when you have a lot of stuff to concatenate.



## **Pascal Strings**



- Pascal Strings "fixed" stores byte count in first byte
  - They can contain zeros and are not null terminated.
    - Because a byte can only store numbers between 0 and 255
  - Pascal strings
    - Limited to 255 bytes in length
    - Not null terminated
    - Same amount of memory as ASCIZ strings
  - No looping just to figure out the length of your string.
    - It is monumentally faster.
- Used outside of Pascal
  - Old Macintosh OS used Pascal strings everywhere.
  - Many C programs used Pascal strings for speed.
  - Excel uses Pascal Excel are limited to 255 bytes
    - One reason Excel is fast.







 Create a Pascal string literal in your C code, you had to write:

```
char* str = "\006Hello!";
```

- Had to count the bytes by hand, yourself, and hardcode it into the first byte of your string.
  - Lazy programmers would do this, and have slow programs:

```
char* str = "*Hello!";
str[0] = strlen(str) - 1;
```

- Notice in this case you've got a string that is null terminated (the compiler did that) as well as a Pascal string.
- These are called fucked strings because it's easier than calling them null terminated pascal strings



#### How much do we allocate?



- We have to scan through all the strings once
  - Figuring out how big they are
  - Scan through them again concatenating
- if you use Pascal strings the strlen operation is fast.



## **Better Strcmp?**



- Walks two character strings at a time
  - One by one
    - Byte by Byte
  - Until it finds a difference or until it hits NULL
- Mechanism
  - char \*p1, char \*p2



## **Better Strcmp?**



- What if you pad your strings to 4 bytes?
  - You can use Unsigned Integer compares
  - 4x times faster
  - Add up to 3 bytes more data per string.
  - Is it worth it?



#### File names with directories



- Where is the difference?
  - "C:\code\gam491\instructor\Basics8 -Templates\Basics8\Basics8\A.cpp"
  - "C:\code\gam491\instructor\Basics8 -Templates\Basics8\Basics8\B.cpp"
- After 63 bytes of comparison
  - We find a difference
  - A lot of compares to find the difference







- Write the strings backwards
  - "ppc.A\8scisaB\8scisaB\setalpmeT 8scisaB\rotcurtsni\194mag\edoc\:C"
  - "ppc.B\8scisaB\8scisaB\setalpmeT 8scisaB\rotcurtsni\194mag\edoc\:C"
- After 5 bytes of comparison
  - We find a difference
  - 5 is better than 63



## Strings?




- What if we HASHed the string?
  - If the strings are READ only
  - We are not mutating them
- Convert string to a 32 bit hash number
  - MD5, CRC32, etc
  - Use that as a lookup / compare
    - Find the associated string
- C# and Java use HASH tags for their strings





- Sometimes in Graphics we talk about strings when we really want Glyphs
- Glyphs sprites on a 2D texture sheet that are cut and pasted together

# aaaaaaaaaaaa





## **Thank You!**





• Questions?