Sector Times App for Shutoko Revival Project

Welcome to the DeltaSRP App by Captain Bale! This app is designed to give you detailed, real-time feedback on your lap and sector performance, using a custom gate-based system that divides each of SRP's official time-attack routes into hundreds of timed mini-sectors. It allows you to drive against your own personal bests from the current session or your all-time saved records.

Main Features

- Live Delta Timer: A large, clear display showing your real-time gap to a reference lap (+/- seconds).
- **Dual Reference Modes:** Instantly switch between comparing your live delta against:
 - 1. Your best lap from the **current session**.
 - 2. Your all-time **Personal Best (PB)** saved to disk.
- **Server-Accurate Sector Times:** Displays official sector and lap times as they are reported by the server.
- **Automatic PB Saving:** Automatically saves your new personal best **VALID** laps to disk for future use (overwrites any saved old time, only one save per car per route is possible).
- Shareable PBs: The save file system is simple, allowing you to share your best lap files with friends to race against their times (found in the savedtimes folder in the main app directory, which can be opened through the app: Settings → Saved PB's → Open Saved Times Folder). Since this might overwrite your own saved time file, make sure to back it up somewhere in case you need it again.

How to Use

- 1. **Install the App:** Place the sector times app folder into your assettocorsa/apps/lua/ directory or simply drag and drop the zip file into Content Manager.
- 2. Enable the App: In Assetto Corsa, enable the "Sector Times" app from your apps sidebar.

The Main Window

The main window is split into three sections:

1. Live Delta Display:

o At the top, you'll find the main Current Lap Delta display. This number updates in real-time as you drive through the 500+ timing gates placed per route.



Next to the title is a button that allows you to toggle the reference mode



2. Current Lap:

- This section shows the official server sector times for the lap you are currently driving.
- The numbers in [brackets] are the reference times you are being compared against (either your session best or your all-time PB).

```
Route: Belt Inner
     1:29.85 [1:28.27] (+1.58)
      -:--.- [2:15.98]
      -:--. [0:58.53]
LAP: -:--.- [4:42.78]
```

When in Session PB mode there is a button that toggles between "Fastest Lap" and "Best Sectors" mode. This determines whether the app will display your best individual sectors from the session (and show a combined ideal lap time*) or simply display the sectors from your fastest complete lap this session.

3. Last Lap:

This section displays the final, official server times for the lap you just completed.

Settings

The settings button can be found on the top-right edge of the app window.

Settings Tab

• Appearance

- **Show Window Background:** Toggles the transparent background of the main app window on or off for a cleaner look.
- o Font Size: Change the font size of main UI elements

• Behavior

 Count invalid laps towards session PB's: If this is checked, a lap marked as (invalid) by the server can still become your session PB if it's the fastest time you've set in that session. This does not affect your all-time saved PB; only valid laps can be saved.

• Personal Best Management

- o This section shows the current car and loop you are driving on.
- Delete saved PB for this loop: This button will delete the all-time personal best .json file for the specific car and route combination currently displayed. Use this if you want to start fresh and set a new PB.