



ID	BR-001	BR-002	BR-003
Summary	[Desktop] The "Reset app state" button doesn't update the application to the default state in the burger menu on the inventory page	[Desktop] The "Reset app state" button doesn't update the application to the default state in the burger menu on the shopping cart page	[Accessibility - Keyboard navigation][Desktop] Unavailable visual highlighting in the focus element with the keyboard navigation on the burger menu
Environment	Web / Chrome 121	Web / Chrome 122	Web / Chrome 123
Severity	Major	Major	Major
Priority	Hight	Hight	Medium
Status	Awaiting Review	Awaiting Review	Awaiting Review
Preconditions:	1. User is logged in	1. User is logged in	1. User is logged in
Steps to Reproduce:	1. Open the inventory page 2. Set filter 3. Add products to shopping cart 4. Open the burger menu 5. Click on the button "Reset app state"	1. Open the inventory page 2. Set filter 3. Add products to the shopping cart 4. Open the shopping cart 4. Open the burger menu 5. Click on the button "Reset app state."	1. Open the inventory page 2. Open the burger menu 3. Press the Tab key to navigate through all interactive elements up to the end 4. Observe the visual highlighting
Expected Result:	The application state is reset successfully and all filters, cart items, and sorting settings are cleared and reset to default state	The application state is reset successfully and all filters, cart items, and sorting settings are cleared and reset to default state	All interactive elements are clearly visible and visually highlighted when focused
Actual Result:	The cart is cleaned, and the shopping_cart_badge is removed. Products are still marked as selected by the modified button "Remove". To add a product again, the user must unclick the "Remove" button. Sorting by the pre-selected filter remains.	The shopping_cart_badge is removed. Products remain in the shopping cart. The user has the opportunity to continue placing the order with all previously selected products.	The visual appearance of interactive elements remains unselected. The user needs to count the "Tab" clicks to understand which button they clicked. All keyboard navigation works properly.

ID	BR-001	BR-002	BR-003
Summary	[Desktop] The "Reset app state" button doesn't update the application to the default state in the burger menu on the inventory page	[Desktop] The "Reset app state" button doesn't update the application to the default state in the burger menu on the shopping cart page	[Accessibility - Keyboard navigation][Desktop] Unavailable visual highlighting in the focus element with the keyboard navigation on the burger menu
Attachments:			
Notes			