
Levels in Modern Computers

Prof Rajeev Barua E-A 001 -- Slide set 1



Software development process





or after that, using itself.

Levels in modern computers



Computers can be understood at various levels.

 Reason: Master the complexity of machines. There is no human alive who know everything about a Pentium chip!!

Two types of levels:

- Hardware: tangible objects.
- Software: sequences of code (at any level).

Software and HW are logically equivalent. Can do a task in either, but may be more efficient in one of them.

Hardware levels



Example levels in modern computers:

- Material Science level
 - Fabricate Silicon and doped Silicon to produce electrical materials
- Solid-state physics
 - Design transistors from materials with desired electrical properties
- Device level
 - Design gates from transistors thus implementing basic boolean functions
- Digital logic design
 - Build hardware modules from gates.
 Lang: Boolean algebra & Register-transfer language
- Micro-architecture level
 Lang: Micro-program or direct execution
 - How to implement instructions using hardware modules
 - How do instructions manipulate the machine's state
- Instruction-set architecture (ISA) level Lang: Machine code
 - Specification of the bit formats of machine code instructions

Software levels



Example levels in modern computers:

- Instruction-set architecture (ISA) level Lang: Machine code
 - Duplicated as the lowest software level
 - Specification of machine-code program (composing of 0's and 1's)
- Operating System level
 Lang: Machine code with OS features
 - Provide computer management facilities using ISA to running programs.
- Assembly language level Lang: Assembly language code
 - A text-based human-readable version of machine code.
 - o Programming languages are compiled into assembly language.
- Higher-level language (HLL) levels
 Lang: HLL code
 - o Eg: C, C++, Java, Python, ...
 - These are translated by compilers into assembly language or machine code.
- Algorithm level
 Lang: Pseudo-code
 - How to design methods to implement tasks efficiently using high-level languages.

Languages and machines per level



Related concept: Languages and machines per level

Each level there is a view of the machine, and a language to explain concepts at that level.

L0 is machine language of lowest level, Machine is M0

L1 is a higher level language more convenient for people to use.

Especially relevant for:

L0: machine code, M0 is CPU

L1: high-level language (HLL) program, M1 is interpreter software for HLL program

Translation and interpretation



To execute it, we have two choices:

- Translation: L1->L0 offline
- Interpretation: On the fly translation by replacing L1 instr by L0 sequence.


Eg:

- C is compiled to machine code
- But Python is interpreted using its interpreter
- Java is a hybrid: it is compiled to Java bytecode, which is interpreted.


Example of interpreted languages



Pure interpreted language:



Hybrid:



No machine code is produced for input program in either case! But interpreters and compilers are in machine code.

Interpreted vs. compiled languages



Advantages of Interpreted languages:

- Instrumentable
- Portable across platforms

(Used for internal corporate code or externally visible SaaS software services)

Advantages of Compiled languages:

- Protect intellectual property (IP) by not revealing source code.
- Much faster (especially vs. Python)

(Used for externally distributed software, or when speed is important.)

Translation vs interpretation generalized.



<u>Advantages of translation</u>: More efficient. No hardware needed. Faster <u>Advantages of interpretation</u>: L1 programs are portable, L0 are not.

Corresponding machine M1 (may be a hypothetical construct only, not built!)

Why not built in some cases?

Not efficient. Simple instructions => simple hardware.

Why have multiple layers?

So long as a converter between levels is available, person can control computer operation at a higher level, without knowing how lower levels (actual hardware) work.