







 PuTTY (inactive)

```
R2(config)#ip dhcp pool sales
R2(dhcp-config)#network 1.0.0.0 255.0.0.0
R2(dhcp-config)#default-router 1.0.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 1.0.0.1 1.0.0.10
R2(config)#ip dhcp pool hr
R2(dhcp-config)#network 29.0.0.0 255.0.0.0
R2(dhcp-config)#default-router 29.0.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 29.0.0.1 29.0.0.10
R2(config)#ip dhcp pool mgmt
R2(dhcp-config)#network 129.23.0.0 255.255.0.0
R2(dhcp-config)#default-router 129.23.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 129.23.0.1 129.23.0.50
R2(config)#ip dhcp pool production
R2(dhcp-config)#network 212.25.0.0 255.255.255.0
R2(dhcp-config)#default-router 212.25.0.1
R2(dhcp-config)#dns-server 8.8.8.8
R2(dhcp-config)#exit
R2(config)#ip dhcp excluded-address 212.25.0.1 212.25.0.100
R2(config)#
R2(config)#
```



Google Chrome isn't your default browser

Set as default

PuTTY (inactive)

```
R1(config-if)#exi
R1(config)#
R1(config)#
R1(config)#
R1(config)#int e0/1
R1(config-if)#ip helper-address 172.50.0.2
R1(config-if)#
```

R3

```
R3(config-if)#exi
R3(config)#int e0/1
R3(config-if)#ip helper-address 12.0.0.1
R3(config-if)#
```

R4

```
exi
R4(config)#int e0/1
R4(config-if)#ip helper-address 222.215.0.1
R4(config-if)#
```

R5

```
exi
R5(config)#int e0/1
R5(config-if)#ip helper-address 62.0.0.1
R5(config-if)#
```

MGMT

Physical



01 : 00 : 00

