



Philippine Christian University



Sampaloc I, Dasmariñas, Cavite

<https://dasma.pcu.edu.ph>

Configuring SSH Remote Access on Ubuntu Server

Objective

Set up an Ubuntu Server with SSH (Secure Shell) remote access and connect to it from a host desktop machine using Bridged Network mode.

Operating System Installation

Install Ubuntu Server

1. Start the VM and boot from the Ubuntu Server ISO
2. Follow the installation wizard:
 - Profile setup: Create a user account (e.g., server / server123)
 - Install OpenSSH server: **Check this option** (Important!)
 - Selected software: **None** (Standard Ubuntu Server)
3. Wait for installation to complete and reboot

Network Configuration

Configure Network Mode

For VirtualBox:

1. Power off the VM (if running)
2. Go to **Settings** → **Network**
3. **Adapter 1**: Enable Network Adapter
4. **Attached to**: Select **Bridged Adapter**
5. **Name**: Select your host's physical network adapter (Wi-Fi/Ethernet)
6. Click **OK**

For VMware:

1. Power off the VM
2. Go to **VM Settings** → **Network Adapter**

3. Select **Bridged** mode

4. Click **OK**

Install/Verify SSH Server

Server: Install SSH on the server (if not already installed):

- `sudo systemctl status ssh` – for checking the SSH status.
- `sudo apt update` – updating the your server.
- `sudo apt install openssh-server -y` –installing the SSH.
- `sudo systemctl enable ssh` – enabling the SSH to your unit. (SERVER/DESKTOP)
- `sudo systemctl start ssh` – starting the SSH to your unit. (SERVER/DESKTOP)

Bridged makes the server behave like a separate PC in your LAN.

1. Find the Server's IP

Inside the VM, run:

```
Sample@UBUNTU-DESKTOP:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP group default qlen 1000
    link/ether 08:00:27:9b:8c:ca brd ff:ff:ff:ff:ff:ff
    inet 192.168.1.4/24 brd 192.168.1.255 scope global dynamic noprefixroute enp0s3
        valid_lft 83602sec preferred_lft 83602sec
    inet6 2001:4451:b00:2000:d76c:1af2:a10c:f36d/64 scope global temporary dynamic
        valid_lft 179068sec preferred_lft 83386sec
    inet6 2001:4451:b00:2000:a00:27ff:fe9b:8cca/64 scope global dynamic mngtmpadr proto kernel_r
        valid_lft 179068sec preferred_lft 92668sec
    inet6 fe80::a00:27ff:fe9b:8cca/64 scope link proto kernel_ll
        valid_lft forever preferred_lft forever
Sample@UBUNTU-DESKTOP:~$
```

From the desktop, connect to the server: `ssh username@192.168.1.120`

2. Connect from Desktop

From your host desktop:

```
Sample@UBUNTU-DESKTOP:~$ ssh Server@192.168.1.14
Server@192.168.1.14's password:
Welcome to Ubuntu 24.04.1 LTS (GNU/Linux 6.8.0-79-generic x86_64)

 * Documentation:  https://help.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

System information as of Mon Sep  8 11:24:38 PM UTC 2025

System load:          0.0
Usage of /:           5.1% of 48.91GB
Memory usage:         5%
Swap usage:           0%
Processes:            139
Users logged in:      1
IPv4 address for enp0s3: 192.168.1.14
IPv6 address for enp0s3: 2001:4451:b00:2000:a00:27ff:fe57:bc4a

Expanded Security Maintenance for Applications is not enabled.

136 updates can be applied immediately.
To see these additional updates run: apt list --upgradable

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

Last login: Mon Sep  8 22:52:07 2025 from 192.168.1.4
Server@UBUNTU-SERVER:~$
```

Submission Requirements

1. Screenshots (labeled clearly):

- VM network settings showing Bridged Adapter
- Server IP address (output of `ip a` or `hostname -I`)
- SSH service status (`sudo systemctl status ssh`)
- Successful SSH connection from host
- Verification commands executed inside VM

2. Submission Format:

- Single PDF file
- Include name, student ID, and date
- All screenshots with brief explanation
- Upload to your portfolio website.

UBUNTU SERVER SSH REMOTE ACCESS LAB

Name: Keith Jared C. Romasanta

Student ID: 2024301930

Course/Year/Section: BSIT 3B

Date Submitted: September 2, 2026

Instructor: Johneros P. Puyo

1 OBJECTIVES (5 POINTS) *Check all that apply:*

- ☒ ☐ ~~Create and configure a Virtual Machine with Ubuntu Server~~
- ☒ ☐ ~~Configure Bridged Network Adapter for network access~~
- ☒ ☐ ~~Determine and verify the server's IP address~~
- ☒ ☐ ~~Install OpenSSH Server and enable the service~~
- ☒ ☐ ~~Establish successful SSH connection from host machine~~
- ☒ ☐ ~~Execute verification commands to confirm remote access~~

2 HARDWARE & SOFTWARE REQUIREMENTS (5 POINTS)

Item	Specification
Host Operating System	Ubuntu server 26
Virtualization Software (VirtualBox/VMware)	Oracle VM VirtualBox 7.0
Ubuntu Server Version	Ubuntu server 26.04LTS
VM Name	keith
RAM Allocated	4096MB
Storage Allocated	100GB
Network Mode	Host only adaptor
SSH Client Used	OpenSSH client through a terminal using shs command

3 VM CONFIGURATION

Setting	Value
VM Name	UBUNTU-SERVER
OS Type	Ubuntu (64-bit)
Memory	4096 MB

Hard Disk	100 GB
Network Adapter	Host only adapter

4. NETWORK CONFIGURATION

Commands Executed:

```
sudo systemctl status ssh
sudo apt update
sudo apt install openssh-server -y
sudo systemctl enable ssh
sudo systemctl start ssh
ip a
```

Server IP Address: keith

Network Interface: 192.168.56.101

6. REMOTE CONNECTION

Connection Details:

Parameter	Value
Server IP	192.168.56.101
Username	keith
SSH Port	Ssh keith@192.168.56.101

Documentation:

Create Virtual Machine

▼ Name and Operating System

Name: romasantaserver ✓

Folder: C:\Users\COLLEGE STUDENT\VirtualBox VMs

ISO Image: C:\Users\COLLEGE STUDENT\Downloads\ubuntu-26.04-live-server-amd64.iso

Edition:

Type: Linux

Version: Ubuntu (64-bit)

☐ Skip Unattended Installation

> Unattended Install

> Hardware

> Hard Disk

Help Guided Mode Back Finish Cancel

Create Virtual Machine

> Name and Operating System

▼ Unattended Install

Username and Password

Username: vboxuser ✓

Password: ●●●●●●

Repeat Password: ●●●●●●

Additional Options

Product Key: #####-#####-#####-###

Hostname: romasantaserver ✓

Domain Name: myguest.virtualbox.org

☐ Install in Background

☐ Guest Additions

Guest Additions ISO: <not selected>

> Hardware

> Hard Disk

Help Guided Mode Back Finish Cancel

Create Virtual Machine

> Name and Operating System

> Unattended Install

✓ Hardware

Base Memory: 4096 MB

Processors: 4

☐ Enable EFI (special OSes only)

> Hard Disk

Help Guided Mode Back Finish Cancel

Create Virtual Machine

> Name and Operating System

> Unattended Install

> Hardware

✓ Hard Disk

☒ Create a Virtual Hard Disk Now

Hard Disk File Location and Size

C:\Users\COLLEGE STUDENT\VirtualBox VMs\yomasantaserver\yomasantaserver.vdi

100.00 GB

Hard Disk File Type and Variant

VDI (VirtualBox Disk Image)

☐ Pre-allocate Full Size



☐ Split into 2GB parts



☐ Use an Existing Virtual Hard Disk File


Pelones_elective3.vdi (Normal, 100.00 GB)



☐ Do Not Add a Virtual Hard Disk



Help Guided Mode Back Finish Cancel




























```
romasantaserver [Running] - Oracle VM VirtualBox
File Machine View Input Devices Help

Ubuntu 26.04 LTS keith tty1

keith login: keith
Password:
Welcome to Ubuntu 26.04 LTS (GNU/Linux 7.0.0-30-generic x86_64)

 * Documentation:  https://docs.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

System information as of Wed Sep  2 07:32:38 AM UTC 2026

System load: 0.02      Memory usage: 7%    Processes:   152
Usage of /:  14.7% of 47.93GB  Swap usage:  0%    Users logged in: 0

Expanded Security Maintenance for Applications is not enabled.

53 updates can be applied immediately.
To see these additional updates run: apt list --upgradable

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

keith@keith:~$ ip a
1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN group default qlen 1000
    link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00
    inet 127.0.0.1/8 scope host lo
        valid_lft forever preferred_lft forever
    inet6 ::1/128 scope host noprefixroute
        valid_lft forever preferred_lft forever
2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc pfifo_fast state UP group default qlen 1000
    link/ether 08:00:27:2b:d5:d0 brd ff:ff:ff:ff:ff:ff
    altname enx0800272bd5d0
    inet 192.168.56.101/24 metric 100 brd 192.168.56.255 scope global dynamic enp0s3
        valid_lft 468sec preferred_lft 468sec
    inet6 fe80::a00:27ff:fe2b:d5d0/64 scope link proto kernel_l1
        valid_lft forever preferred_lft forever
keith@keith:~$ ip a _
```

```
RomasantaElective3 [Running] - Oracle VM VirtualBox
File Machine View Input Devices Help

Sep 2 15:38

keith@keith: ~ -- ssh keith@192.168.56.101

*
keith@192.168.56.101's password:
Welcome to Ubuntu 26.04 LTS (GNU/Linux 7.0.0-30-generic x86_64)

 * Documentation:  https://docs.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

System information as of Wed Sep  2 07:35:28 AM UTC 2026

System load: 0.3      Memory usage: 8%    Processes:   156
Usage of /:  14.7% of 47.93GB  Swap usage:  0%    Users logged in: 0

Expanded Security Maintenance for Applications is not enabled.

53 updates can be applied immediately.
To see these additional updates run: apt list --upgradable

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo pro status

keith@keith:~$
```