
ALTER USER

유저를 변경할 때는 ALTER USER 'username'을 입력하여 USER를 변경합니다. username 뒤에는 여러 가지 option이 추가될 수 있습니다.




[그림] USER 이름 변경 결과 화면

| E | | · | laou@localhost:/PostgreSQ |
|-------------------------------------|-----------------|--|--|
| File Edit V | iew Search Term | inal Help | |
| postgres=# ` Role name | \du | List of roles Attributes | Member of |
| postgres test1 test2 test3 | Superuser, Cre | ate role, Create DB, Rep | olication {} {} {} {} |
| | password clear | RENAME TO TEST4; ed because of role renam | ne |
| Role name | | List of roles Attributes | Member of |
| postgres test1 test2 test4 | Superuser, Cre | ate role, Create DB, Rep | olication {} {} {} {} |
| postgres=# | Ĭ | | |

[User 비밀번호 변경]

1 | ALTER USER TEST2 WITH PASSWORD 'test22';


[그림] USER 비밀번호 변경 결과화면



[User 생성, 권한 변경]

1 | ALTER USER TEST1 WITH CREATEUSER REPLICATION;

[그림] USER 생성, 권한 변경 결과화면



DROP USER

USER를 삭제할 때는 ALTER USER 'name'을 입력하여 USER를 삭제합니다.

1 DROP USER name

[User 삭제]

1 DROP USER TEST2;

[그림] User 삭제 결과화면

| ☑ daou@loca | | | | | lhost:/PostgreSQL/9.4 | |
|---------------------------------------|---------------------|-------------------------------|------------|-------------|-----------------------|--|
| File Edit V | iew Search | Terminal Help | | | | |
| oostgres=# Role name | \du | List of r Attribu | | | Member of | |
| postgres test1 test2 test4 | | Create role, C Replication | Create DB, | Replication | 0 0 0 0 | |
| postgres=# DROP ROLE postgres=# | DROP USER TE \du | ST2; | | | | |
| Role name | I | List of r Attribu | | 1 | Member of | |
| postgres test1 test4 | | Create role, C Replication | Create DB, | Replication | {} {} {} | |
| postgres=# | | | | | | |