TRC404 – BurnAndMint Version

TRC404 Master

(compatible with JettonMaster)

Attributes:

total_supply admin_address content jetton_wallet_code nft_collection_address mintable

Receive message:

- 1.DeployMaster
- 2. Mint
- 3.ChangeAdmin
- 4. Change Freemint Config
- 5.Withdraw

TRC404 wallet

(compatible with JettonWallet)

Attributes:

jetton_balance owner_address jetton_master_address jetton_wallet_code nft_collection_address Owned_nft_dict Owned_nft_number

Receive message:

1.Transfer2.Internal_transfer3.Add_one_ft_and_nft4.Reduce_one_ft_and_nft5.Add_nft_list

TRC404 nftCollection (compatible with nftCollection)

Attributes:

owner_address
next_item_index,
collection_content
nft_item_code
royalty_params
total_supply,
jetton_wallet_code
Master_addres
Owned_nft_limit

Receive message:

- 1. InitCollection
- 2. AddNftSupply
- 2. ReduceOneNft
- ${\it 3. Request Transfer One Ff And Nft}\\$
- 4. ChangeOwnedNftLimit
- 5. GetRoyaltyParams
- 6. ChangeRoyaltyParams

TRC404 nftltem

(compatible with nftltem)

Attributes:


nft item index collection address owner_address nft content


Receive message:


- 1. DeployNftItem
- 2. TransferNftItem
- 3. BurnNftltem
- 4. GetStaticData

Permission settings


- 1. Master contract, only the administrator address can mint FT, modify the administrator address, modify free Mint parameters, and withdraw funds.
- 2. Wallet contracts only accept messages sent from wallet contract, or master contract, or Nft Item contracts from other users.
- 3. The Collection contract only accepts messages sent by the Wallet contract or Nft Item contract.
- 5. For NftItem contracts, only messages sent from the owner address are accepted.









Transfer FT –branch 1 (only transfer n FT, no NFT will be transfer)




Transfer FT –branch 2 (transfer FT, sender burn 1 NFT)





Transfer FT –branch 4 (transfer FT, sender burn n NFT, receiver mint m NFT) n and m>=1



Transfer NFT

