


Week1 Lab2

Basic configuration Router


1.Topology



2. Table Address

Device	Interface	IP Address / Prefix	Default Gateway
R1	G0/0/0	192.168.0.1 /24	N/A
		2001:db8:acad::1 /64	
		fe80::1	
	G0/0/1	192.168.1.1 /24	
		2001:db8:acad:1::1 /64	
		fe80::1	
	Loopback0	10.0.0.1 /24	
		2001:db8:acad:2::1 /64	
		fe80::1	
PC-A	NIC	192.168.1.10 /24	192.168.1.1
		2001:db8:acad:1::10 /64	fe80::1
Server	NIC	192.168.0.10 /24	192.168.0.1
		2001:db8:acad::10 /64	fe80::1

3. Physical connect



4.PC - A config

PC-A

Physical Desktop Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.1.10

Subnet Mask 255.255.255.0

Default Gateway 192.168.1.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address 2001:DB8:ACAD:1::10 / 64

Link Local Address FE80::203:E4FF:FE71:4258

Default Gateway FE80::1

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

5. Server configuration

Server

Physical Services Desktop Programming Attributes

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.0.10
Subnet Mask 255.255.255.0
Default Gateway 192.168.0.1
DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address 2001::DB8:ACAD::10 / 64
Link Local Address FE80::207:ECFF:FEA5:6286
Default Gateway FE80::1
DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5
Username
Password

6.Router configuration

- IPv4

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface gigabitethernet 0/0/0
Router(config-if)#ip address 192.168.0.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#exit
Router(config)#interface gigabitethernet 0/0/1
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown

Router#show ip interface brief
Interface                IP-Address      OK? Method Status
Protocol
GigabitEthernet0/0/0     192.168.0.1     YES manual up
up
GigabitEthernet0/0/1     192.168.1.1     YES manual up
```

- IPv6

```
R1(config)#ipv6 unicast-routing
R1(config)#interface g0/0/0
R1(config-if)#ipv6 address 2001:db8:acad::1/64
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#interface g0/0/1
R1(config-if)#ipv6 address 2001:db8:acad:1::1/64
R1(config-if)#no shutdown
```

```
R1#show ipv6 interface brief
GigabitEthernet0/0/0      [up/up]
    FE80::207:ECFF:FE60:B801
    2001:DB8:ACAD::1
GigabitEthernet0/0/1      [up/up]
    FE80::207:ECFF:FE60:B802
    2001:DB8:ACAD:1::1
```