

Constructor

The constructor in Angular is used for object creation and dependency injection. It is called before lifecycle hooks, and we should avoid placing business logic or API calls inside it.

ngOnChanges

ngOnChanges is a lifecycle hook in Angular that is called whenever the value of an input property (@Input) changes. It is used to detect and handle changes in data coming from a parent component.

ngOnInit

ngOnInit is a lifecycle hook that runs once after component initialization. It is mainly used for performing initialization tasks such as API calls and setting up initial data.

Used for: API calls ,Initial data setup

ngDoCheck

ngDoCheck is a lifecycle hook that runs whenever Angular performs change detection and is used for custom change detection.

ngAfterContentInit

ngAfterContentInit is a lifecycle hook in Angular that is called once after the parent content is projected into the child component using ng-content.

ngAfterContentChecked

ngAfterContentChecked is called every time Angular checks the parent content inside the child component.

ngAfterViewInit

ngAfterViewInit is a lifecycle hook that is called once after the component's view (HTML/UI) is fully initialized.

ngAfterViewChecked

ngAfterViewChecked is a lifecycle hook that is called every time Angular checks the component's view (UI/HTML).

ngOnDestroy

ngOnDestroy is a lifecycle hook that is called just before the component is destroyed. It is used for cleanup activities.

constructor

↓

ngOnChanges

↓

ngDoCheck

↓

ngOnInit

↓

ngAfterContentInit

↓

ngAfterContentChecked

↓

ngAfterViewInit

↓

ngAfterViewChecked

↓

ngOnDestroy

Constructor is used to create the component and inject dependencies.

After that, Angular sets input data from the parent, which triggers ngOnChanges.

ngDoCheck runs to detect changes during every cycle.

ngOnInit is called once after the component is initialized.

Then ngAfterContentInit is called once after the parent content is projected into the child component.

ngAfterContentChecked runs whenever Angular checks the projected content.

ngAfterViewInit is called once after the component's view (UI) is initialized.

ngAfterViewChecked runs whenever Angular checks the view.

Finally, ngOnDestroy is called before the component is destroyed.

1. constructor → create component
2. ngOnChanges → parent data
3. ngDoCheck → checking
4. ngOnInit → start work
5. ngAfterContentInit → parent content ready
6. ngAfterContentChecked → content checking
7. ngAfterViewInit → UI ready
8. ngAfterViewChecked → UI checking
9. ngOnDestroy → end / cleanup