



labs.surennetwork.com/legacy/topology
Notifications
SUREN NETWORK
PLAY WITH TECHNOLOGIES
SSH - TE
e0/0
ROUTER
50.0.0.1
ROUTER
*Oct 10 08:53:34.373: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface IP-Address OK? Method Status Prot
ocol
Ethernet0/0 unassigned YES TFTP up up
Ethernet0/1 unassigned YES TFTP down down
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
ROUTER#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip address 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#exit
ROUTER#
*Oct 10 08:54:53.420: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interface brief
Interface IP-Address OK? Method Status Protocol
Ethernet0/0 50.0.0.1 YES manual up up
Ethernet0/1 unassigned YES TFTP down down
Ethernet0/2 unassigned YES TFTP down down
Ethernet0/3 unassigned YES TFTP down down
ROUTER#
Router Configuration
Physical
01 : 00 : 00
START


WhatsApp
PNETLab | Topology
Ask Gemini
labs.surennetwork.com/legacy/topology
Notifications
ROUTER
Press RETURN to get started.
User Access Verification
Username: console
Password:
ROUTER>
ROUTER>
ROUTER>en
Password:
Router Configuration
Physical
01 : 00 : 00
START


Router Configuration (1).pdf
File D:/Downloads/Router%20Configuration%20(1).pdf
3 of 3
labs.surennetwork.com/legacy/topology
Notifications
QEMU (Win)
Computer
Cisco IP Communic...
50.0.0.1 - PuTTY
User Access Verification
Password:
ROUTER>
ROUTER>
PuTTY (inactive)
User Access Verification
Username: console
Password:
ROUTER>
ROUTER>
ROUTER>en
Password:
% Password: timeout expired!
Password:
ROUTER#
ROUTER#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#line vty 0 3
ROUTER(config-line)#transport input telnet
ROUTER(config-line)#password telnet
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#exit
ROUTER#
ROUTER#
*Oct 10 16:30:43.935: %SYS-5-CONFIG_I: Configured from console by console on console
ROUTER#
About
Help
Open
Cancel
User Access Verification
Password:
ROUTER>en
Password:
ROUTER#
4:37 PM
Router Configuration
Physical
01 : 00 : 00
START