

VMware Workstation Pro 25H2

Get it [here](#)

VMware Workstation Pro is now free for commercial, educational, and personal use. You no longer require a license key, making it a major update for developers and IT pros.

Adopting a calendar-based naming (Year 2025, H2) for clearer releases, features many improvements in performance and compatibility and security fixes.

Author of the article: *Iker Elg. Alzaa*


#VMware #WorkstationPro #Hypervisors



VMware Workstation is a desktop virtualisation software that lets you run multiple operating systems (like Windows, Linux, or macOS) as

virtual machines (VMs) simultaneously on a single physical computer, creating isolated environments for development, testing, and learning without needing separate hardware.

It acts as a hosted hypervisor, simulating hardware to run these different OSes side-by-side with your main system, offering features like snapshots to save and restore states easily.



What is new

VMware Fusion Pro 25H2 provides the following new capabilities.

- Introducing *dictTool*, a command-line tool to examine and modify VMware configuration files (such as a vmx file or user preferences file)
- Added support for USB 3.2
- Added support for virtual hardware version 22
- Added support for new guest operating systems
- Red Hat Enterprise Linux 10
- Fedora Linux 42
- OpenSUSE Leap 16.0 (RC)
- SUSE Linux 16 (Beta)

- Debian 13
- Oracle Linux 10
- VMware ESX 9.0 (on Intel-based systems)
- macOS Tahoe (on Intel-based systems)

Added support for new host operating systems.

- macOS Tahoe (Intel and Apple Silicon)

Requirements

The physical computer on which you install Workstation Pro is called the host system and its operating system is called the host operating system.

To run Workstation Pro, the host system and the host operating system must meet specific hardware and software requirements.

To get a detailed information about the requirements go [here](#).

Processor

You must install Workstation Pro on a host system that meets certain processor requirements.

The following host systems are supported:

- A compatible 64-bit x86/AMD64 CPU launched in 2011 or later
- For specific Host Operating Systems (HOS), refer to the vendor's recommended processor requirements

For supported processors to run 64-bit guest operating systems, the host system must use one of the following processors types.

- An AMD CPU with AMD-V support
- An Intel CPU with VT-x support

If you have an Intel CPU that has VT-x support, you must verify that VT-x support is enabled in the host system BIOS.

Operative System

You can install Workstation Pro on Windows and Linux host operating systems.

Hyper-V hypervisors and VMware Workstation can coexist perfectly on Windows systems.

Memory

The minimum memory required on the host system is 2 GB of RAM. 4 GB and above is recommended.

Display

The host system must have a 16-bit or 32-bit display adapter. Use the latest graphics driver recommended for the host system.

3D benchmarks, such as 3DMark '06, might not render correctly or at all when running Windows

Vista or Windows 7 virtual machines on some graphics hardware.

VMware Workstation Pro REST API

VMware Workstation Pro REST API allow you to interact programmatically with the core VMware hypervisor and virtual machines.

You can send standard GET, PUT, POST, and DELETE requests through HTTP and HTTPS to control configuration and deployment options.

For example, you can use VMware Workstation Pro REST API to perform clone and power operations. You can perform network-related operations, such as to create and update virtual NIC configurations and to retrieve IP addresses from the virtual machine. You can also configure shared folders. Response payloads are delivered in JSON format.