Assignment Kit for Program 7



Personal Software Process (PSP) for Engineers: Part II

The Software Engineering Institute (SEI) is a federally funded research and development center sponsored by the U.S. Department of Defense and operated by Carnegie Mellon University.

This material is approved for public release. Distribution limited by the Software Engineering Institute to attendees.

Personal Software Process for Engineers: Part II Assignment Kit for Program 7

Overview

Overview

This assignment kit covers the following topics.

Section	See Page
Prerequisites	2
Program 7 requirements	3
Significance	5
Prediction interval	6
Assignment instructions	7
Guidelines and evaluation criteria	16
Operational specification template and instructions	17
Functional specification template and instructions	19
State specification template and instructions	21
Logic specification template and instructions	23

Prerequisites

Reading

• Chapter 10, 11, 12

Program 7 requirements

Program 7 requirements

Using PSP2.1, write a program to

- calculate the correlation between two sets of numbers x and y
- calculate the significance of that correlation
- calculate the linear regression parameters β_0 and β_1 for a set of *n* pairs of data,
- given an estimate, x_k calculate an improved prediction, y_k where $y_k = \beta_0 + \beta_1 x_k$
- calculate the 70% prediction interval for that estimate

Table 1 contains historical estimated and actual data for 10 programs. For program 11, the developer has estimated a proxy size of 386 LOC.

Thoroughly test the program. At a minimum, run the following four test cases.

- Test 1: Perform the required calculations defined above using estimated proxy size and actual added and modified size in Table 1. Use an estimates proxy size of $x_k = 386$ in producing the improved estimate and prediction interval.
- Test 2: Perform the required calculations defined above using estimated proxy size and actual development time in Table 1. Use an estimated proxy size of $x_k = 386$ in producing the improved estimate and prediction interval.
- Test 3: Perform the required calculations defined above using estimated proxy size and actual added and modified size for your programs 3-6. Use an x_k = estimated proxy size for program 7.
- Test 4: Perform the required calculations defined above using estimated proxy size and actual development time for your programs 3-6. Use an x_k = estimated proxy size for program 7.

Program Number	Estimated Proxy Size	Plan Added and Modified Size	Actual Added and Modified Size	Actual Development Hours
1	130	163	186	15.0
2	650	765	699	69.9
3	99	141	132	6.5
4	150	166	272	22.4
5	128	137	291	28.4
6	302	355	331	65.9
7	95	136	199	19.4
8	945	1206	1890	198.7
9	368	433	788	38.8
10	961	1130	1601	138.2

Table 1

Program 7 requirements, Continued

Test	Parameter	Expected Value	Actual Value
Test 1	$r_{x,y}$	0.954496574	
	r^2	0.91106371	
	significance	1.77517E-05	
	$oldsymbol{eta}_0$	-22.55253275	
	$oldsymbol{eta}_1$	1.727932426	
	y_k	644.4293838	
	Range	230.0017197	
	UPI (70%)-	874.4311035	
	LPI (70%)	414.427664	
Test 2	$r_{x,y}$	0.933306898	
	r^2	0.871061766	
	significance	7.98203E-05	
	eta_0	-4.038881575	
	$oldsymbol{eta}_1$	0.16812665	
	\mathcal{Y}_k	60.85800528	
	Range	27.55764748	
	UPI (70%)-	88.41565276	
	LPI (70%)	33.3003578	
Test 3	$r_{x,y}$	n/a	
	r^2	n/a	
	significance		
	$oldsymbol{eta}_0$	n/a	
	$oldsymbol{eta}_{\scriptscriptstyle 1}$	n/a	
	\mathcal{Y}_k	n/a	
	Range	n/a	
	UPI (70%)-	n/a	
	LPI (70%)	n/a	
Test 4	$r_{x,y}$	n/a	
	r^2	n/a	
	significance		
	$oldsymbol{eta}_0$	n/a	
	$oldsymbol{eta}_1$	n/a	
	\mathcal{Y}_k	n/a	
	Range	n/a	
	UPI (70%)-	n/a	
	LPI (70%)	n/a	

Table 2


Significance

The significance test

The significance test determines the likelihood that a strong correlation is random, and is therefore of no practical significance.

For example, a data set with only two points will always have an $r^2 = 1$, but this correlation is not significant.

Student t-Distribution



Calculating significance

The procedure for calculating the correlation significance is as follows.

1. Compute the value of *x*, such that

$$x = \frac{|r_{x,y}| \sqrt{n-2}}{\sqrt{1 - r_{x,y}^{2}}}$$

where

- $r_{x,y}$ is the correlation
- *n* is the number of data points
- 2. Find the probability p by numerically integrating the t distribution for n-2 degrees of freedom, from 0 to x.
- 3. Calculate the *significance* (tail area) as 1-2*p. (The area under the curve from -x to +x is twice the area from 0 to x, or 2*p; the remaining area in the upper and lower tails is 1-2*p).

A tail area ≤ 0.05 is considered as strong evidence that there is a relationship.

A tail area ≥ 0.2 indicates a relationship that is due to chance.

Prediction interval

Prediction interval

The prediction interval provides a likely range around the estimate.

- A 70% prediction interval gives the range within which 70% of the estimates will fall.
- It is not a forecast, only an expectation.
- It only applies if the estimate behaves like the historical data.

It is calculated from the same data used to calculate the regression parameters.

Prediction interval procedure

To calculate the prediction interval, use the following steps.

- 1. Calculate the *Range* for a 70% interval.
- 2. Calculate the UPI as $y_k + Range(70\%)$.
- 3. Calculate the LPI as $y_k Range(70\%)$.

The formula for calculating the prediction range is

Range =
$$t(0.35, dof)\sigma \sqrt{1 + \frac{1}{n} + \frac{(x_k - x_{avg})^2}{\sum_{i=1}^{n} (x_i - x_{avg})^2}}$$

where

- x is your historical data
- *n* is the number of historical data points
- t(0.35, dof) is the value of x for a t distribution for n 2 degrees of freedom and p = 0.35

The formula for calculating the standard deviation term is

$$\sigma = \sqrt{\left(\frac{1}{n-2}\right)\sum_{i=1}^{n} \left(y_i - \beta_0 - \beta_1 x_i\right)^2}$$

where

- x, y are your historical data
- *n* is the number of historical data points

Assignment instructions

Assignment instructions

Before starting program 7, review the top-level PSP2.1 process script below to ensure that you understand the "big picture" before you begin. Also, ensure that you have all of the required inputs before you begin the planning phase.

PSP2.1 Process Script

Purpose	To guide the development of module-level programs
Entry Criteria	- Problem description
	- PSP2.1 Project Plan Summary form
	- Size Estimating template
	- Historical size and time data (estimated and actual)
	- Time and Defect Recording logs
	- Defect Type, Coding, and Size Measurement standards
	- Stopwatch (optional)

Step	Activities	Description
1	Planning	 Produce or obtain a requirements statement. Use the PROBE method to estimate the added and modified size and the size prediction interval of this program. Complete the Size Estimating template. Use the PROBE method to estimate the required development time and the time prediction interval. Complete a Task Planning template. Complete a Schedule Planning template. Enter the plan data in the Project Plan Summary form. Complete the Time Recording log.
2	Development	 Design the program. Document the design in the design templates. Review the design, and fix and log all defects found. Implement the design. Review the code, and fix and log all defects found. Compile the program, and fix and log all defects found. Test the program, and fix and log all defects found. Complete the Time Recording log.
3	Postmortem	Complete the Project Plan Summary form with actual time, defect, and size data.

Exit Criteria	- A thoroughly tested program
	- Completed Project Plan Summary form with estimated and actual data
	- Completed Size Estimating and Task and Schedule Planning templates
	- Completed Design templates
	- Completed Design Review and Code Review checklists
	- Completed Test Report template
	- Completed PIP forms
	- Completed Time and Defect Recording logs

Planning phase

Plan program 7 following the PSP2.1 planning phase and the PROBE estimating scripts.

PSP2.1 Planning Script

Purpose	To guide the PSP planning process
Entry Criteria	Problem descriptionPSP2.1 Project Plan Summary form
	 Size Estimating, Task Planning, and Schedule Planning templates Historical size and time data (estimated and actual)
	- Historical size and time data (estimated and actual) - Time Recording log

Step	Activities	Description
1	Program Requirements	 Produce or obtain a requirements statement for the program. Ensure that the requirements statement is clear and unambiguous. Resolve any questions.
2	Size Estimate	 Produce a program conceptual design. Use the PROBE method to estimate the added and modified size of this program. Complete the Size Estimating template and Project Plan Summary form. Calculate the 70% size prediction interval. (You may use a spreadsheet.)
3	Resource Estimate	 Use the PROBE method to estimate the time required to develop this program. Calculate the 70% size prediction interval. (You may use a spreadsheet.) Using the To Date % from the most recently developed program as a guide, distribute the development time over the planned project phases.
4	Task and Schedule Planning	For projects lasting several days or more, complete the Task Planning and Schedule Planning templates.
5	Defect Estimate	 Based on your to-date data on defects per added and modified size unit, estimate the total defects to be found in this program. Based on your <i>To Date %</i> data, estimate the number of defects to be injected and removed by phase.

Exit Criteria	- Documented requirements statement
	- Program conceptual design
	- Completed Size Estimating template
	- For projects lasting several days or more, completed Task and Schedule
	Planning templates
	- Completed Project Plan Summary form with estimated program size,
	development time, and defect data, and the time and size prediction
	intervals
	- Completed Time Recording log

Verify that you have met all of the exit criteria for the planning phase, **then have** an **instructor review your plan**. After your plan has been reviewed, proceed to the development phase.

Use the PROBE method to create size and resource estimates.

PROBE Estimating Script

Purpose	To guide the size and time estimating process using the PROBE method	
Entry Criteria	- Requirements statement	
	- Size Estimating template and instructions	
	- Size per item data for part types	
	- Time Recording log	
	- Historical size and time data	
General	- This script assumes that you are using added and modified size data as the	
	size-accounting types for making size and time estimates.	
	- If you choose some other size-accounting types, replace every "added and	
	modified" in this script with the size-accounting types of your choice.	

Step	Activities	Description
1	Conceptual Design	Review the requirements and produce a conceptual design.
2	Parts Additions	Follow the Size Estimating Template instructions to estimate the parts additions and the new reusable parts sizes.
3	Base Parts and Reused Parts	For the base program, estimate the size of the base, deleted, modified, and added code.Measure and/or estimate the size of the parts to be reused.
4	Size Estimating Procedure	 If you have sufficient estimated proxy size and actual added and modified size data (three or more points that correlate), use procedure 4A. If you do not have sufficient estimated data but have sufficient plan added and modified and actual added and modified size data (three or more points that correlate), use procedure 4B. If you have insufficient data or they do not correlate, use procedure 4C. If you have no historical data, use procedure 4D.
4A	Size Estimating Procedure 4A	 Using the linear-regression method, calculate the β₀ and β₁ parameters from the estimated proxy size and actual added and modified size data. If the absolute value of β₀ is not near 0 (less than about 25% of the expected size of the new program), or β₁ is not near 1.0 (between about 0.5 and 2.0), use procedure 4B.
4B	Size Estimating Procedure 4B	 Using the linear-regression method, calculate the β₀ and β₁ parameters from the plan added and modified size and actual added and modified size data. If the absolute value of β₀ is not near 0 (less than about 25% of the expected size of the new program), or β₁ is not near 1.0 (between about 0.5 and 2.0), use procedure 4C.
4C	Size Estimating Procedure 4C	If you have any data on plan added and modified size and actual added and modified size, set $\beta_0 = 0$ and $\beta_1 =$ (actual total added and modified size to date/plan total added and modified size to date).
4D	Size Estimating Procedure 4D	If you have no historical data, use your judgment to estimate added and modified size.

(continued)

PROBE Estimating Script (Continued)

Step	Activities	Description
5	Time Estimating Procedure	 If you have sufficient estimated proxy size and actual development time data (three or more points that correlate), use procedure 5A. If you do not have sufficient estimated size data but have sufficient plan added and modified size and actual development time data (three or more points that correlate), use procedure 5B. If you have insufficient data or they do not correlate, use procedure 5C. If you have no historical data, use procedure 5D.
5A	Time Estimating Procedure 5A	 Using the linear-regression method, calculate the β₀ and β₁ parameters from the estimated proxy size and actual total development time data. If β₀ is not near 0 (substantially smaller than the expected development time for the new program), or β₁ is not within 50% of 1/(historical productivity), use procedure 5B.
5B	Time Estimating Procedure 5B	 Using the linear-regression method, calculate the β₀ and β₁ regression parameters from the plan added and modified size and actual total development time data. If β₀ is not near 0 (substantially smaller than the expected development time for the new program), or β₁ is not within 50% of 1/(historical productivity), use procedure 5C.
5C	Time Estimating Procedure 5C	 If you have data on estimated – added and modified size and actual development time, set β₀ = 0 and β₁ = (actual total development time to date/estimated – total added and modified size to date). If you have data on plan – added and modified size and actual development time, set β₀ = 0 and β₁ = (actual total development time to date/plan total added and modified size to date). If you only have actual time and size data, set β₀ = 0 and β₁ = (actual total development time to date/actual total added and modified size to date).
5D	Time Estimating Procedure 5D	If you have no historical data, use your judgment to estimate the development time from the estimated added and modified size.
6	Time and Size Prediction Intervals	 If you used regression method A or B, calculate the 70% prediction intervals for the time and size estimates. If you did not use the regression method or do not know how to calculate the prediction interval, calculate the minimum and maximum development time estimate limits from your historical maximum and minimum productivity for the programs written to date.
Exit C	riteria	 Completed estimated and actual entries for all pertinent size categories Completed PROBE Calculation Worksheet with size and time entries Plan and actual values entered on the Project Plan Summary

Development phase

Develop the program following the PSP2.1 development phase script.

PSP2.1 Development Script

Purpose	To guide the development of small programs
Entry Criteria	- Requirements statement
	- Project Plan Summary form with estimated program size and
	development time
	- For projects lasting several days or more, completed Task Planning and
	Schedule Planning templates
	- Time and Defect Recording logs
	- Defect Type standard and Coding standard

Step	Activities	Description
1	Design	 Review the requirements and produce an external specification to meet them. Complete Functional and Operational Specification templates to record this specification. Produce a design to meet this specification. Record the design in Functional, Operational, State, and Logic Specification templates. Record in the Defect Recording log any requirements defects found. Record time in the Time Recording log.
2	Design Review	 Follow the Design Review script and checklist and review the design. Fix all defects found. Record defects in the Defect Recording log. Record time in the Time Recording log.
3	Code	 Implement the design following the Coding standard. Record in the Defect Recording log any requirements or design defects found. Record time in the Time Recording log.
4	Code Review	 Follow the Code Review script and checklist and review the code. Fix all defects found. Record defects in the Defect Recording log. Record time in the Time Recording log.
5	Compile	 Compile the program until there are no compile errors. Fix all defects found. Record defects in the Defect Recording log. Record time in the Time Recording log.
6	Test	 Test until all tests run without error. Fix all defects found. Record defects in the Defect Recording log. Record time in the Time Recording log. Complete a Test Report template on the tests conducted and the results obtained.

Exit Criteria	- A thoroughly tested program that conforms to the Coding standard
	- Completed Design templates
	- Completed Design Review and Code Review checklists
	- Completed Test Report template
	- Completed Time and Defect Recording logs

Verify that you have met all of the exit criteria for the development phase, then proceed to the postmortem phase.

Design review

Review your designs following the PSP2.1 design review script.

PSP2.1 Design Review Script

Purpose	To guide you in reviewing detailed designs
Entry Criteria	- Completed program design documented with the PSP Design templates
	- Design Review checklist
	- Design standard
	- Defect Type standard
	- Time and Defect Recording logs
General	Where the design was previously verified, check that the analyses
	- covered all of the design
	- were updated for all design changes
	- are correct
	- are clear and complete

Step	Activities	Description
1	Preparation	 Examine the program and checklist and decide on a review strategy. Examine the program to identify its state machines, internal loops, and variable and system limits. Use a trace table or other analytical method to verify the correctness of the design.
2	Review	 Follow the Design Review checklist. Review the entire program for each checklist category; do not try to review for more than one category at a time! Check off each item as you complete it. Complete a separate checklist for each product or product segment reviewed.
3	Fix Check	 Check each defect fix for correctness. Re-review all changes. Record any fix defects as new defects and, where you know the defective defect number, enter it in the fix defect space.

Exit Criteria	- A fully reviewed detailed design
	- One or more Design Review checklists for every design reviewed
	- Documented design analysis results
	- All identified defects fixed and all fixes checked
	- Completed Time and Defect Recording logs

Code review

Review your code following the code review script.

Code Review Script

Purpose	To guide you in reviewing programs
Entry Criteria	- A completed and reviewed program design
	- Source program listing
	- Code Review checklist
	- Coding standard
	- Defect Type standard
	- Time and Defect Recording logs
General	Do the code review with a source-code listing; do not review on the screen!

Step	Activities	Description
1	Review	- Follow the Code Review checklist.
		- Review the entire program for each checklist category; do not try to review
		for more than one category at a time!
		- Check off each item as it is completed.
		- For multiple procedures or programs, complete a separate checklist for
		each.
2	Correct	- Correct all defects.
		- If the correction cannot be completed, abort the review and return to the
		prior process phase.
		- To facilitate defect analysis, record all of the data specified in the Defect
		Recording log instructions for every defect.
3	Check	- Check each defect fix for correctness.
		- Re-review all design changes.
		- Record any fix defects as new defects and, where you know the number of
		the defect with the incorrect fix, enter it in the fix defect space.

Exit Criteria	- A fully reviewed source program
	- One or more Code Review checklists for every program reviewed
	- All identified defects fixed
	- Completed Time and Defect Recording logs

Postmortem phase

Conduct the postmortem following the PSP2.1 postmortem script.

PSP2.1 Postmortem Script

Purpose	To guide the PSP postmortem process
Entry Criteria	- Problem description and requirements statement
	- Project Plan Summary form with program size, development time, and
	defect data
	- For projects lasting several days or more, completed Task Planning and
	Schedule Planning templates
	- Completed Test Report template
	- Completed Design templates
	- Completed Design Review and Code Review checklists
	- Completed Time and Defect Recording logs
	- A tested and running program that conforms to the coding and size
	measurement standards

Step	Activities	Description
1	Defect Recording	- Review the Project Plan Summary to verify that all of the defects found in
		each phase were recorded.
		- Using your best recollection, record any omitted defects.
2	Defect Data Consistency	- Check that the data on every defect in the Defect Recording log are accurate and complete.
	·	- Verify that the numbers of defects injected and removed per phase are reasonable and correct.
		- Determine the process yield and verify that the value is reasonable and correct.
		- Using your best recollection, correct any missing or incorrect defect data.
3	Size	- Count the size of the completed program.
		- Determine the size of the base, reused, deleted, modified, added, total,
		added and modified, and new reusable code.
		- Enter these data in the Project Plan Summary form.
4	Time	- Review the completed Time Recording log for errors or omissions.
		- Using your best recollection, correct any missing or incomplete time data.

Exit Criteria	- A thoroughly tested program that conforms to the coding and size
	measurement standards
	- Completed Design templates
	- Completed Design Review and Code Review checklists
	- Completed Test Report template
	- Completed Project Plan Summary form
	- Completed PIP forms describing process problems, improvement
	suggestions, and lessons learned
	- Completed Time and Defect Recording logs

Verify that you have met all of the exit criteria for the PSP2.1 postmortem phase, then submit your assignment.

Submitting your assignment

When you've completed the postmortem phase, submit your assignment package, source code, and test results to the instructor.

The order for the assignment package is

- PSP2.1 Project Plan Summary form
- Test Report template (Use Junit to create complete test class)
- PSP2.1 Design Review checklist
- Design Templates (Operational template and Javadoc)
- Trace table or other analytical method to verify the correctness of the design.
- Code Review checklist
- PIP form
- Size Estimating template
- PROBE Calculation worksheet
- Time Recording log
- Defect Recording log
- source program listing
- · test results
- Upload your code to a GITHUB project, using MAVEN and GIT
- Deploy a running version of your software on Heroku
- Readme.txt file with instructions of how to:
 - Build it with MAVEN package phase (It should compile and run the tests)
 - clone it from GITHUB
 - Access the program in Heroku

Guidelines and evaluation criteria for program 7

Evaluation criteria

Your process report must be

- complete
- legible
- in the specified order

Your process data must be

- · accurate
- precise
- self-consistent

Suggestions

Remember, you should complete this assignment today.

Keep your programs simple. You will learn as much from developing small programs as from large ones.

If you are not sure about something, ask your instructor for clarification.

Software is not a solo business, so you do not have to work alone.

- You must, however, produce your own estimates, designs, code, and completed forms and reports.
- You may have others review your work, and you may change it as a result.
- You should note any help you receive from others in your process report. Log the review time that you and your associates spend, and log the defects found or any changes made.