Client-Server Networking


October, 2025


Presented by

Lucas Ha
Shoaib Mahmood
Victor Wang

Setting up a LAN Chat server

Install LAN OutputMessangerServerSetup software: https://www.outputmessenger.com/lan-messenger-downloads/,






Click "I accept the agreement" to install the application


Setting up a LAN chat server part 2

Select the folder/destination where you want your chat server application to be installed then extract the zip file inside your desired location




Setting up a LAN chat server part 3

After extracting, open the software called "ServerManagerOM"




Setting up a LAN chat server part 4

Once the software is opened, follow the instructions and login with your computer administrator account.




Setting up a LAN chat server part 5

After the software window opens, click on "Networks" in the column on the left, under authorization, click the addition symbol next to "Authorized Networks"



Setting up a LAN chat server part 6


After clicking on the addition symbol, create a network name and select "ok"




Setting up a LAN chat server part 7

Go to "User" on the left column and click on the addition symbol on the top left corner to add a new user.


Name the new user and Click "OK"






Setting up a LAN chat server part 8

Click on the addition icon next to "Chat Rooms" on the top right corner to create a chat room.



Setting up a LAN chat server part 9


Name your chat room and tweak the settings to your desired preferences, make sure to add the usernames to the exact letter and spacing on par of what you named your users.



Setting up a LAN chat server part 10

Get another computer to install the same software and get on the same LAN network as the server computer, they have now become a client, make sure they login with the name given to them on the server computer to be able to access the chat rooms.





Setting up a LAN chat server part 11


Enjoy chatting with others under the same server network!

```
C:\Users\compTech>ipconfig

Windows IP Configuration



Ethernet adapter Ethernet:

   Connection-specific DNS Suffix  . :
   Link-local IPv6 Address . . . . . : fe80::16e:8bb1:776c:d810%13
   IPv4 Address. . . . . . . . . . . : 192.168.0.106
   Subnet Mask . . . . . . . . . . . : 255.255.255.0
   Default Gateway . . . . . . . . . : 192.168.0.1
```




Setting up a Web Server

Now we will set up a web server using an application called "simple web server" which you can install here:





Make sure to install the portable (.zip) file, either 32 or 64 bit depending on your computer.

Extract the zip file to a location of your choice. I will be using a USB drive but your downloads folder should work fine.




After it's extracted, find and run this program






Choose your preferred options and hit “get started”

You should now be here:



Before we make a server, we should create a folder which will hold our HTML page. Go inside your web server's folder and create a folder. I will call it "main server"




Open your computer's notepad and make a simple html page. You can copy mine here or make your own. You don't have to include an image but I will.


File Edit Format View Help

```
<html>
        <body>
                <h1>hello this is lucas HA's basement</h1>
                <img src = "image.png">
        </body>
</html>
```

Now go to File and "Save as"



Save this notepad file to the “main server” file we made earlier. If you want to include an image in the webpage, make sure that image is also in the main server file.




When saving, make sure to name it “index.html” and select “all files”


Go back to the server software and click “new server.” In the options, go to the file path option:



For the file path, choose the “main server” file which should now have your HTML web page. Click “select folder”




For the Port, you can choose any number you want. I will go with "8080."



Now hit Create Server



It should show the server running:



Now go to your browser and type “localhost:portnumber” in this case my port number is 8080, so i will type “localhost:8080”



You should now be inside the HTML web page we created earlier


To connect another device, connect it to the same LAN as the device which is hosting the server. Go into a browser and type:

192.168.0.67:portnumber

"192.168.0.67" represents the IP address of the computer which is hosting the server. The port number is the one you selected. In my case, i will type in:


192.168.0.100:8080


And you should now be inside that same HTML page.
Congratulations, you have made a web server!



Setting up a game LAN Part 1

First step is to connect 2 or more devices to your LAN internet WIFI






Setting up a game LAN Part 2

Download a game like Pocket Tanks with a wifi/LAN connection option for wireless connection for gameplay.




Setting up a game LAN Part 3


Select "WIFI LOBBY" as the option to play



Setting up a game LAN Part 5


If your both connected to the same network, you should see each other's names in the Wifi Lobby, and click invite.






Setting up a game LAN Part 6

After one of the players click invite, the other person should receive a popup/notification for an invite to the game.





Setting up a game LAN Part 6

After clicking accept, enjoy playing a wireless connection against each other under the same LAN/Wifi network!

