TMUX

L = = Ctrl + f

Sessions

Shortcut	Explanation
tmux	Start a new session
tmux new -s mysession or :new -s mysession	Start a new session with the name mysession
tmux kill-session -t mysession	Kill/delete session mysession
tmux fill-session -a	Kill/delete all sessions but the current
tmux fill-session -a -t mysession	Kill/delete all sessions but mysession
L\$	Rename session
Ld	Detach from session
tmux Is / L s	Show all sessions
tmux a	Attach to last session
tmux a -t mysession	Attach to a session with th name mysession
L(Move to previous session
L)	Move to next session

Windows

Shortcut	Explanation
tmux new -s mysession -n mywindow	Start a new session with the name mysession and window mywindow
Ic	Create window
1,	Rename current window
1&	Close current window
Гр	Previous window
In	Next window
10 9	Switch/select window my number
swap-window -s 2 -t 1	Reorder window, swap window number 2(src) and 1(dst)
swap-window -t -1	Move current window to the left by one position

Panes

Shortcut	Explanation
L;	Toggle last active Panes
L % / L V	Split pane vertically
L"/LS	Split pane horizontally
L{	Move the current pane left
L}	Move the current pane right
L (, ,)	Switch to pane to the direction
setw synchronize-panes	Toggle synchronize-panes (send command to all panes)
L Spacebar	Toggle between pane layouts
Lo	Switch to next pane
Lq	Show pane numbers
Lq09	Switch/select pane by number
Lz	Toggle pane zoom
L!	Convert pane into a window
L ()	Resize current pane height (hold three keys)
L ()	Resize current pane width (hold three keys)
Lx	Close current pane

Copy Mode

Shortcut	Explanation
setw -g mode-keys vi	Use vi keys in buffer
L[Enter copy mode
L PgUp	Enter copy mode and scroll one page up
q	Quit mode
Spacebar	Start selection
Esc	Clear selection
Enter	Copy selection
L]	Paste contents of buffer_0
show-buffer	Display buffer_0 contents
capture-pane	Copy entire visible contents of pane to a buffer

Shortcut	Explanation
list-buffers	Show all buffers
choose-buffer	Show all buffers and paste selected
save-buffer buf.txt	Save buffer contents to buf.txt
delete-buffer -b 1	Delete buffer_1

Misc

Shortcut	Explanation
L:	Entere command mode
set -g OPTION	Set OPTION for all sessions
setw -g OPTION	Set OPTION for all windows
tmux info	Show every session, window, pane, etc
L?	Show shortcuts

General

Shortcut	Explanation
C-f C-o	Rotate through the panes
C-f C-z	Suspend the current client
C-f Space	Select next layout
C-f!	Break pane to a new window
C-f "	Split window vertically
C-f #	List all paste buffers
C-f \$	Rename current session
C-f %	Split window horizontally
C-f &	Kill current window
C-f'	Prompt for window index to select
C-f (Switch to previous client
C-f)	Switch to next client
C-f,	Rename current window
C-f -	Delete the most recent paste buffer
C-f.	Move the current window

Shortcut	Explanation
C-f /	Describe key binding
C-f 0	Select window 0
C-f 1	Select window 1
C-f 2	Select window 2
C-f 3	Select window 3
C-f 4	Select window 4
C-f 5	Select window 5
C-f 6	Select window 6
C-f 7	Select window 7
C-f 8	Select window 8
C-f 9	Select window 9
C-f:	Prompt for a command
C-f;	Move to the previously active pane
C-f =	Choose a paste buffer from a list
C-f?	List key bindings
C-f C	Customize options
C-f D	Choose and detach a client from a list
C-f E	Spread panes out evenly
C-f M	Clear the marked pane
C-f [Enter copy mode
C-f]	Paste the most recent paste buffer
C-f c	Create a new window
C-f d	Detach the current client
C-f f	Search for a pane
C-fi	Display window information
C-f m	Toggle the marked pane
C-f n	Select the next window
C-f o	Select the next pane
C-f p	Select the previous window
C-f q	Display pane numbers

Shortcut	Explanation
C-f s	Choose a session from a list
C-f w	Choose a window from a list
C-f x	Kill the active pane
C-f z	Zoom the active pane
C-f {	Swap the active pane with the pane above
C-f}	Swap the active pane with the pane below
C-f ~	Show messages
C-f DC	Reset so the visible part of the window follows the cursor
C-f PPage	Enter copy mode and scroll up
C-f Up	Select the pane above the active pane
C-f Down	Select the pane below the active pane
C-f Left	Select the pane to the left of the active pane
C-f Right	Select the pane to the right of the active pane
C-f M-1	Set the even-horizontal layout
C-f M-2	Set the even-vertical layout
C-f M-3	Set the main-horizontal layout
C-f M-4	Set the main-vertical layout
C-f M-5	Select the tiled layout
C-f M-n	Select the next window with an alert
C-f M-o	Rotate through the panes in reverse
C-f M-p	Select the previous window with an alert
C-f M-Up	Resize the pane up by 5
C-f M-Down	Resize the pane down by 5
C-f M-Left	Resize the pane left by 5
C-f M-Right	Resize the pane right by 5
C-f C-Up	Resize the pane up
C-f C-Down	Resize the pane down
C-f C-Left	Resize the pane left
C-f C-Right	Resize the pane right
C-f S-Up, S-Down, S-Left, S-Right	Move the visible part of the window up, down, left, right